



EMC[®] Avamar[®] 7.2 for IBM DB2

User Guide

302-001-793

REV 02

Copyright © 2001-2015 EMC Corporation. All rights reserved. Published in USA.

Published August, 2015

EMC believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

The information in this publication is provided as is. EMC Corporation makes no representations or warranties of any kind with respect to the information in this publication, and specifically disclaims implied warranties of merchantability or fitness for a particular purpose. Use, copying, and distribution of any EMC software described in this publication requires an applicable software license.

EMC², EMC, and the EMC logo are registered trademarks or trademarks of EMC Corporation in the United States and other countries. All other trademarks used herein are the property of their respective owners.

For the most up-to-date regulatory document for your product line, go to EMC Online Support (<https://support.emc.com>).

EMC Corporation
Hopkinton, Massachusetts 01748-9103
1-508-435-1000 In North America 1-866-464-7381
www.EMC.com

CONTENTS

Figures	7
Tables	9
Preface	11
Chapter 1	Introduction 15
	Architecture..... 16
	Data Domain system support..... 16
	Multiple DB2 versions on a single host..... 17
	DPF support..... 17
	Log files..... 17
	Backup..... 17
	Backup types..... 17
	Data deduplication optimization..... 18
	Restore and recovery..... 18
	Redirected restores..... 19
	Table space restore and recovery from Avamar Administrator..... 19
	Concurrent backups and restores..... 20
	DB2 CLP support..... 20
	DPF backup and restore..... 20
	DPF backup..... 20
	DPF restore and recovery..... 21
	Archived log backup and restore..... 21
	Multi-streaming..... 21
Chapter 2	Installation 23
	Preparing to install the Avamar Plug-in for DB2..... 24
	System requirements..... 24
	DB2 server requirements..... 24
	Downloading the software..... 24
	Installing the Avamar file system client..... 25
	Installing, upgrading, and uninstalling on HP-UX..... 25
	Installing the Avamar Plug-in for DB2 on HP-UX..... 25
	Upgrading the Avamar Plug-in for DB2 on HP-UX..... 26
	Uninstalling the Avamar Plug-in for DB2 on HP-UX..... 26
	Installing, upgrading, and uninstalling on IBM AIX..... 27
	Installing the Avamar Plug-in for DB2 on IBM AIX..... 27
	Upgrading the Avamar Plug-in for DB2 on IBM AIX..... 27
	Uninstalling the Avamar Plug-in for DB2 on IBM AIX..... 28
	Installing, upgrading, and uninstalling on Linux..... 29
	Installing the Avamar Plug-in for DB2 on Linux..... 29
	Upgrading the Avamar Plug-in for DB2 on Linux..... 30
	Uninstalling the Avamar Plug-in for DB2 on Linux..... 30
	Installing, upgrading, and uninstalling on Solaris..... 31
	Installing the Avamar Plug-in for DB2 on Solaris..... 31
	Upgrading the Avamar Plug-in for DB2 on Solaris..... 32

	Uninstalling the Avamar Plug-in for DB2 on Solaris	33
	Installing, upgrading, and uninstalling on Windows	33
	Installing the Avamar Plug-in for DB2 on Windows	34
	Upgrading the Avamar Plug-in for DB2 on Windows	34
	Uninstalling the Avamar Plug-in for DB2 on Windows	35
Chapter 3	Backup	37
	Preparing the database for backup	38
	Configuring automatic backups for DB2 transaction logs	38
	Creating the Avamar Plug-in for DB2 flag file	38
	Performing offline backups	39
	Performing online backups	39
	Preparing for DPF backups	40
	Configuring the backup agent for DPF backups	40
	DPF backup limitations	40
	Performing on-demand backups	41
	Scheduling backups	43
	Creating a dataset	43
	Creating a group	46
	Enabling scheduled backups	47
	Monitoring backups	47
	Canceling backups	48
Chapter 4	Restore and Recovery	49
	Backup naming conventions	50
	Backup labels and image names for a database backup	50
	Backup labels and image names for log backups	51
	Restoring DB2 databases to the original location	51
	Restoring offline backups	51
	Restoring online backups that include archive logs	54
	Restoring online backups that do not include archive logs	56
	Restoring only the archive logs	59
	Recovering a database	62
	Restoring DB2 databases to a different client	63
	Setting flags for automatic storage databases	63
	Rollforward after a redirected restore to a different host	64
	Restoring the database to a different client	64
	Rolling the database forward	68
	Restoring and recovering DPF	68
	Restoring database partitions to the original location	69
	Restoring database partitions to a different location	70
	Recovering partitions	73
	Restoring table spaces in a stand-alone DB2 environment	75
	Restoring table spaces in a DB2 DPF environment	79
	Recovering retired clients	82
	Disaster recovery	84
	Recovering the DB2 application	84
	Recovering the DB2 server	84
	Recovering the DB2 server in a DPF environment	85
Chapter 5	Backup and Restore with DB2 CLP	87
	Using DB2 CLP for backups and restores	88
	Backup label and image names	89

	Avamar Plug-in for DB2 flag file configuration	89
	Specifying DB2 vendor parameters	89
	Backing up databases from the DB2 CLP	90
	Example command to back up a database in offline mode	90
	Example command to back up a database in online mode	91
	Example command to back up a table space in online mode	92
	Restoring databases and table spaces from the DB2 CLP	93
	Specifying multiple sessions for a restore from the DB2 CLP	93
	Performing redirected restores from the DB2 CLP	93
	Example procedure to restore an instance to a different instance	93
	Example restore that uses an automatically generated script	94
	Restoring backup images from Avamar versions before 7.0	95
	Recovering DB2 with the DB2 CLP	96
	DB2 CLP limitations	96
	Setting the expiration and retention for backups	97
Appendix A	Plug-in Options	99
	Plug-in options	100
	Performance options	100
	Backup options	101
	Restore options	102
	Table space restore option	104
	DB2 vendor parameters	104
Appendix B	Troubleshooting	109
	Troubleshooting backup problems	110
	Troubleshooting installation and configuration problems	110
	Installing the Avamar Plug-in for DB2 in the default directory fails ..	110
	Resolving a network hostname might result in a time-out error	110
	Troubleshooting DB2 CLP backup and restore problems	111
	Adjusting the time gap between DB2 CLP operations	111
	Backup does not complete in DPF configuration	111
	Cleaning up processes and resources after a DB2 CLP operation	111
	DB2 CLP fails due to time-out in communication response	111
	Recovery of a dropped database fails with error code 30	112
	Using an invalid Avamar Plug-in for DB2 flag file returns an error	113
	Use of signal handles does not cleanly stop DB2 CLP operations ...	113
	Troubleshooting restore problems	114
	Adjusting the base timeline for a log restore	114
	Recover fails if LOGARCHOPT1 is more than 30 characters	114
	Restore fails with a “Failed to initiate the restore operation” error..	115
	Restore fails while retrieving snapview and metadata	115
	Restore fails when search for backup images takes too long	116
	Specifying backup and restore options as normal text	116
Glossary		119

FIGURES

1	Avamar Plug-in for DB2 configuration.....	16
2	Backup label and image names.....	50
3	Avamar software and DB2 CLP process flow.....	88

FIGURES

TABLES

1	Revision history.....	11
2	Command to back up a database in offline mode.....	91
3	Command to back up a database in online mode.....	91
4	Command to back up a table space in online mode.....	92
5	Performance options.....	100
6	Backup plug-in options.....	101
7	Restore plug-in options.....	102
8	DB2 vendor parameters.....	104

PREFACE

As part of an effort to improve its product lines, EMC periodically releases revisions of its software and hardware. Therefore, some functions described in this document might not be supported by all versions of the software or hardware currently in use. The product release notes provide the most up-to-date information on product features.

Contact your EMC technical support professional if a product does not function properly or does not function as described in this document.

Note

This document was accurate at publication time. Go to EMC Online Support (<https://support.EMC.com>) to ensure that you are using the latest version of this document.

Purpose

This guide describes how to install, configure, administer, and use the Avamar Plug-in for DB2.

Audience

The audience for this guide includes DB2 system and database administrators.

Revision history

The following table presents the revision history of this document.

Table 1 Revision history

Revision	Date	Description
01	June, 2015	Initial release of Avamar 7.2.
02	August, 2015	GA release of Avamar 7.2.

Related documentation

The following EMC publications provide additional information:

- *EMC Avamar Administration Guide*
- *EMC Avamar and EMC Data Domain System Integration Guide*
- *EMC Avamar Operational Best Practices*
- *EMC Avamar Product Security Guide*
- *EMC Avamar Release Notes*

Special notice conventions used in this document

EMC uses the following conventions for special notices:

NOTICE

Addresses practices not related to personal injury.

Note

Presents information that is important, but not hazard-related.

Typographical conventions

EMC uses the following type style conventions in this document:

Bold	Use for names of interface elements, such as names of windows, dialog boxes, buttons, fields, tab names, key names, and menu paths (what the user specifically selects or clicks)
<i>Italic</i>	Use for full titles of publications referenced in text
<code>Monospace</code>	Use for: <ul style="list-style-type: none"> • System code • System output, such as an error message or script • Pathnames, file names, prompts, and syntax • Commands and options
<i>Monospace italic</i>	Use for variables
Monospace bold	Use for user input
[]	Square brackets enclose optional values
	Vertical bar indicates alternate selections - the bar means “or”
{ }	Braces enclose content that the user must specify, such as x or y or z
...	Ellipses indicate nonessential information omitted from the example

Where to get help

The Avamar support page provides access to licensing information, product documentation, advisories, and downloads, as well as how-to and troubleshooting information. This information may enable you to resolve a product issue before you contact EMC Customer Support.

To access the Avamar support page:

1. Go to <https://support.EMC.com/products>.
2. Type a product name in the **Find a Product** box.
3. Select the product from the list that appears.
4. Click the arrow next to the **Find a Product** box.
5. (Optional) Add the product to the **My Products** list by clicking **Add to my products** in the top right corner of the **Support by Product** page.

Documentation

The Avamar product documentation provides a comprehensive set of feature overview, operational task, and technical reference information. Review the following documents in addition to product administration and user guides:

- Release notes provide an overview of new features and known limitations for a release.
- Technical notes provide technical details about specific product features, including step-by-step tasks, where necessary.
- White papers provide an in-depth technical perspective of a product or products as applied to critical business issues or requirements.

Knowledgebase

The EMC Knowledgebase contains applicable solutions that you can search for either by solution number (for example, esgxxxxx) or by keyword.

To search the EMC Knowledgebase:

1. Click the **Search** link at the top of the page.
2. Type either the solution number or keywords in the search box.
3. (Optional) Limit the search to specific products by typing a product name in the **Scope by product** box and then selecting the product from the list that appears.
4. Select **Knowledgebase** from the **Scope by resource** list.
5. (Optional) Specify advanced options by clicking **Advanced options** and specifying values in the available fields.
6. Click the search button.

Online communities

Visit EMC Community Network at <http://community.EMC.com> for peer contacts, conversations, and content on product support and solutions. Interactively engage online with customers, partners and certified professionals for all EMC products.

Live chat

To engage EMC Customer Support by using live interactive chat, click **Join Live Chat** on the **Service Center** panel of the Avamar support page.

Service Requests

For in-depth help from EMC Customer Support, submit a service request by clicking **Create Service Requests** on the **Service Center** panel of the Avamar support page.

Note

To open a service request, you must have a valid support agreement. Contact your EMC sales representative for details about obtaining a valid support agreement or with questions about your account.

To review an open service request, click the **Service Center** link on the **Service Center** panel, and then click **View and manage service requests**.

Facilitating support

EMC recommends that you enable ConnectEMC and Email Home on all Avamar systems:

- ConnectEMC automatically generates service requests for high priority events.
- Email Home emails configuration, capacity, and general system information to EMC Customer Support.

Your comments

Your suggestions will help us continue to improve the accuracy, organization, and overall quality of the user publications. Send your opinions of this document to DPAD.Doc.Feedback@emc.com.

Please include the following information:

- Product name and version
- Document name, part number, and revision (for example, 01)
- Page numbers

- Other details that will help us address the documentation issue

CHAPTER 1

Introduction

This chapter includes the following topics:

• Architecture	16
• Backup	17
• Restore and recovery	18
• Concurrent backups and restores	20
• DB2 CLP support	20
• DPF backup and restore	20
• Archived log backup and restore	21
• Multi-streaming	21

Architecture

The EMC® Avamar® Plug-in for DB2 provides a complete deduplication backup and recovery solution for IBM DB2 servers. The Avamar Plug-in for DB2 works with the Avamar server, the Avamar client, and the DB2 API to back up DB2 databases and logs


You can back up DB2 data to and restore DB2 data from an Avamar server or an EMC® Data Domain® system. The Avamar Plug-in for DB2 serves as a backup module and the Avamar server or Data Domain system as a storage device.

The Avamar Plug-in for DB2 supports backups and restores of DB2 single or multiple instance configurations and DB2 configurations that implement DB2 Database Partitioning Feature (DPF).

Each DB2 server host requires the installation of the Avamar Plug-in for DB2 and an Avamar file system client. You can back up and restore DB2 databases by using Avamar Administrator or the DB2 Command Line Processor (CLP).

The following figure shows a configuration in which the Avamar Plug-in for DB2 backs up or restores DB2 databases to or from an Avamar server or a Data Domain system.

Figure 1 Avamar Plug-in for DB2 configuration



Data Domain system support

The Avamar Plug-in for DB2 supports backups to and restores from Data Domain systems.

You can back up DB2 data to a Data Domain system by using Avamar Administrator or by using the DB2 CLP. Metadata for the backup is stored on the Avamar server.

You can restore backups from a Data Domain system the same way you restore backups from the Avamar server. There are no extra steps. You can follow the same restore procedure whether the data is located on the Avamar server or on a Data Domain system.

The *EMC Avamar and EMC Data Domain System Integration Guide* provides more information about configuring Data Domain systems for use with Avamar systems.

Multiple DB2 versions on a single host

The Avamar Plug-in for DB2 supports multiple versions of the DB2 software. For example, the Avamar Plug-in for DB2 can support DB2 10.1 and DB2 9.7 on the same host. The Avamar Plug-in for DB2 also supports multiple DB2 instances within a single DB2 software installation.

DPF support

The Avamar Plug-in for DB2 supports backups and restores in configurations which use DPF. A DPF configuration allows you to partition a database across multiple servers or within a large Symmetric Multi-Processor (SMP) server.

The catalog node or partition is where you run the `CREATE DATABASE` command and where the backup process runs. All other partitions are called noncatalog nodes or partitions.

Log files

The Avamar Plug-in for DB2 creates log files during backup and restore operations. These log files are for debugging purposes.

Backup and restore operations from Avamar Administrator create the `avdb2.log` file in the `install-directory/var/clientlogs` directory. Backup and restore operations from the DB2 CLP create log files in the directory you specify with the `--logfile` option in the flag file.

Note

If the `--logfile` option is not specified in the Avamar Plug-in for DB2 flag file, the logs are generated under the `install-dir/var/clientlogs` directory.

Backup

The Avamar Plug-in for DB2 allows you to perform backups from Avamar Administrator or from the DB2 Command Line Processor (CLP).

Backup types

The Avamar Plug-in for DB2 allows you to use Avamar Administrator and the DB2 CLP to perform full and incremental backups.

The Avamar Plug-in for DB2 supports the following types of backups:

- Full backups from Avamar Administrator
- Full, incremental, and delta backups from the DB2 CLP
- Table space backups from the DB2 CLP
- Online backups

You can perform an online backup while the database is active. During this type of backup, users and applications can connect to the database and perform transactions. Online backups can either include or exclude archived logs.

- **Offline backups**

You can perform an offline backup while the database is inactive. Offline backups do not allow connections to the database.

- **On-demand or scheduled backups from Avamar Administrator.**

You can perform either on-demand or scheduled backups while the database is online or offline.

Data deduplication optimization

The Avamar Plug-in for DB2 supports the `dedup_device` option.

The `dedup_device` option for the `db2 backup database` command is available in the following DB2 versions:

- DB2 10
- DB2 9.7 FixPack 3
- DB2 9.5 FixPack 8

The `dedup_device` option optimizes the format of data that is backed up to a deduplication device. The Avamar Plug-in for DB2 includes support for the `dedup_device` option for backups you run from Avamar Administrator or the DB2 CLP.

- From Avamar Administrator, you specify the `Optimize backup images` option.
- From the DB2 CLP, you specify the `dedup_device` option with the `db2 backup db` command.

Restore and recovery

The Avamar Plug-in for DB2 supports DB2 database restores from both online and offline backups.

You can restore and recover a database only while the database is offline. You cannot restore and recover a database that is online with connections. The restore and recovery operation automatically establishes a connection to the specified database. The connection terminates after the restore operation completes.

You can identify whether the backup is an online or offline backup by its backup label name. The Avamar Plug-in for DB2 uses a naming convention that specifies the type of backup. [Backup naming conventions on page 50](#) provides more information.

The Avamar Plug-in for DB2 restores and recovers databases and table spaces. The Avamar Plug-in for DB2 supports the following restore and recovery options from Avamar Administrator:

- **Restore and roll forward database**
- **Restore only**
- **Restore only archive logs from an online backup**
- **Recover**

The Avamar Plug-in for DB2 includes the following recovery type options:

- **End of logs**

- **Point in Time**
- **End of Backup**

[Restore options on page 102](#) provides more information about restore and recover options available from Avamar Administrator.

Redirected restores

The Avamar Plug-in for DB2 supports redirected restores. A redirected restore enables you to restore a database to a different location on the original client or to a different client altogether. You can restore data from one instance to a different instance.

When you restore a database to a different location, you can only select one database for the restore operation. When performing a redirected restore, the restore target can be the same client from which the backup was originally taken or a different client. A redirected restore to the same client, creates a clone of the original database. The new database contains the same contents of the original database. A redirected restore to a different client, requires that the operating system version and DB2 version on the target client be the same version as on the source client.

A non-automatic storage database (ASM) redirected restore that you perform with Avamar Administrator sets the table space container pathname to the DB2 defaults. If the database contains a user-defined container pathname to a table space, the redirected restore redefines the default pathname. This process requires adequate space on the partition.

The Avamar Plug-in for DB2 supports redirected restores of automatic storage table spaces. To perform redirected restores of automatic storage table spaces requires you to change the storage and database pathnames by passing attributes to the restore operation. [Restore and Recovery on page 49](#) provides more information about setting attributes to restore automatic storage table spaces.

You cannot restore automatic storage table spaces and non-automatic storage table spaces in the same restore operation.

Table space restore and recovery from Avamar Administrator

The granular recovery feature enables you to restore one or more table spaces from a full database backup. During a full database backup from Avamar Administrator, the Avamar Plug-in for DB2 runs the `db2 list history` command, which compiles a list of backed-up table spaces. The Avamar Plug-in for DB2 then uses this list of table spaces for granular recovery operations.

You can perform a table space restore and recovery while the database is online or offline. The exception is the SYSCATSPACE table space. You must perform a SYSCATSPACE table space restore and recovery while the database is offline.

You must use the `DB2 rollforward` command to manually roll the table space forward after you restore a table space from an offline backup or a DPF environment.

An end of backup or point-in-time recovery of a table space leaves the table space in a backup pending state. When a table is in a backup pending state, the database is read-only. You must not make any modifications to the table space. After performing an end of backup or point-in-time recovery of a table space, you must perform an online or offline backup to reset the table space state.

You can restore a renamed table space by using the `renamed_tablespace_list` option.

The following restrictions apply to the granular recovery feature:

- The Avamar Plug-in for DB2 does not support the end of logs, point-in-time, or end of backup recovery types for a table space in a DPF environment.
- DB2 does not support restores of a table space to a database other than the one from which the backup was taken. You cannot restore a table space to a different location on the same host or to a different host.
- The Avamar Plug-in for DB2 does not support restores of dropped table spaces.

Concurrent backups and restores

The Avamar Plug-in for DB2 supports a maximum of six concurrent backup or restore operations. Each backup or restore operation can run multiple data sessions to or from the Avamar server or the Data Domain system.

All backup images that you create by specifying multiple sessions use a sequence number as an extension. The sequence number identifies the backup piece. After a successful backup, the Avamar Plug-in for DB2 represents all backup pieces from all backup sessions as one backup image or label.

You can restore backups that you create with multiple sessions in a single restore session. The Avamar Plug-in for DB2 restores the entire backup image even when you select only one backup piece. To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

[Multi-streaming on page 21](#) provides more information about running multiple data sessions.

DB2 CLP support

You can use the DB2 CLP for backup, restore, recovery, and roll forward operations.

The Avamar Plug-in for DB2 supports the `db2 backup`, `db2 restore`, `db2 recover`, and `db2 rollforward` commands. [Backup and Restore with DB2 CLP on page 87](#) provides more information.

DPF backup and restore

The Avamar Plug-in for DB2 supports backups and restores of DB2 database partitions.

DPF backup

The Avamar Plug-in for DB2 backs up database partitions that are local to the catalog node or remote (located on remote nodes).

To back up database partitions, the Avamar Plug-in for DB2 backup process first connects to the database that you select for backup and runs a query to determine configuration details:

- If the query determines that database partition is local, the backup process continues on the DB2 server.
- If the query determines that the database partition is on a remote node, the Avamar Plug-in for DB2 forwards the backup request to the remote node's host. The host, then acts with the DB2 backup request at the remote host.

For DPF restore operations from Avamar Administrator, the Avamar Plug-in for DB2 limits the selection of DPF nodes to one node and one database. The limitation of one DPF node

at a time on a host also applies to restore operations from the DB2 CLP. [DB2 CLP limitations on page 96](#) provides more information.

The rollforward and recovery operations of DPF nodes from either Avamar Administrator or the DB2 CLP must be run in DPF mode and must be run at the catalog node.

DPF restore and recovery

The Avamar Plug-in for DB2 supports database partition restores in configurations which use the DPF.

Unlike the backup process, which must run only from the catalog partition, the restore operation runs on each partition:

- To restore partitions from the catalog partition, you perform a restore to the original location.
- To restore partitions from non-catalog partitions, you perform a restore to a different location.

For DPF restore operations from Avamar Administrator, the Avamar Plug-in for DB2 limits the selection of DPF nodes to one node and one database. The limitation of one DPF node at a time on a host also applies to restore operations from the DB2 CLP. [DB2 CLP limitations on page 96](#) provides more information.

The rollforward and recovery operations of DPF nodes from either Avamar Administrator or the DB2 CLP must be run in DPF mode and must be run at the catalog node.

Archived log backup and restore

The Avamar Plug-in for DB2 supports backups of archived transaction logs, which you can later use for rollforward operations.

DB2 transaction logs keep records of database changes. DB2 software provides circular and archive logging:

- Circular logging supports full offline database backups.
- Archive logging supports online database backups and rollforward recovery.

The IBM DB2 documentation provides more information about circular and archive logging.

You can configure the DB2 server to back up a transaction log as soon as it is archived. During a recovery or rollforward operation, the DB2 server requests the restore of archived logs that are not available on the system from the Avamar Plug-in for DB2. To skip the overhead process of searching for the available saved archived logs, you can use the Avamar file system plug-in instead of the DB2 plug-in to restore missing archived logs before you restore the database. Then specify the location of the log files when you perform a database rollforward operation.

Multi-streaming

The Avamar Plug-in for DB2 enables you to use multiple data streams for backups and restores. DB2 supports the use of multiple data streams (or sessions) to back up or restore database objects. You can specify multiple sessions for backups and restores from Avamar Administrator and the DB2 CLP.

The use of multiple data sessions for a backup or restore increases system performance when you back up or restore a large database. Multi-streaming, however, can place

additional demands on computer hardware and resources beyond the base requirements for the Avamar Plug-in for DB2.

CHAPTER 2

Installation

This chapter includes the following topics:

- [Preparing to install the Avamar Plug-in for DB2](#)24
- [Installing, upgrading, and uninstalling on HP-UX](#) 25
- [Installing, upgrading, and uninstalling on IBM AIX](#)27
- [Installing, upgrading, and uninstalling on Linux](#) 29
- [Installing, upgrading, and uninstalling on Solaris](#) 31
- [Installing, upgrading, and uninstalling on Windows](#) 33

Preparing to install the Avamar Plug-in for DB2

Review the system requirements for Avamar Plug-in for DB2 to ensure that the environment meets these requirements before you perform the installation. You must download the Avamar file system client and Avamar Plug-in for DB2 packages from the Avamar server.

System requirements

Before you install the Avamar Plug-in for DB2, ensure that the environment meets all software and hardware requirements.

Client compatibility requirements are available in the *EMC Avamar Compatibility and Interoperability Matrix* on EMC Online Support at <https://support.EMC.com>. The requirements in the matrix include supported operating systems and application versions. The Avamar file system client and the Avamar Plug-in for DB2 that you install on the host must be the same version number.

DB2 server requirements

Ensure that the environment meets DB2 requirements. You must have operating system root privileges on the computer that hosts the DB2 server.

The Avamar server must be operational and accessible to the DB2 server on a network. To verify network connectivity, open a command shell on the DB2 server and type the following command:

```
ping Avamar_server
```

where *Avamar_server* is the network hostname or IP address of the Avamar server.

Downloading the software

Download the installation package for the Avamar Plug-in for DB2 from the Avamar server, and then save the package to a temporary directory.

Procedure

1. Log in to the DB2 server with the necessary privileges to perform an installation.
2. Open a web browser and type the following URL:

```
http://Avamar_server
```

where *Avamar_server* is the DNS name or IP address of the Avamar server.

The **EMC Avamar Web Restore** page appears.

3. Click **Downloads**.

The **Downloads** list appears.

4. Click **+** next to the platform heading for the DB2 server.
5. Click **+** next to the operating system heading for the DB2 server.
6. Click the link for the Avamar Plug-in for DB2 installation package.
7. Save the Avamar Plug-in for DB2 installation package to a temporary directory.

Installing the Avamar file system client

Install the appropriate Avamar file system client before you install the Avamar Plug-in for DB2.

Procedure

- For HP-UX, IBM AIX, Linux, and Solaris systems, follow the instructions in the *EMC Avamar Backup Clients User Guide*.
- For Windows systems, follow the instructions in the *EMC Avamar for Windows Server User Guide*.

Installing, upgrading, and uninstalling on HP-UX

You can install, upgrade, and uninstall the Avamar Plug-in for DB2 on HP-UX.

Installing the Avamar Plug-in for DB2 on HP-UX

You can use the `swinstall` command to install the Avamar Plug-in for DB2 in the default `var` directory or in a new location. You can specify a new location for the `var` directory during the Avamar Client for HP-UX installation by using the `-x ask=true` option with the `swinstall` command.

When you install the Avamar Plug-in for DB2 after you install the Avamar Client for HP-UX, the plug-in installation does not automatically use the same location for the `var` directory that you specified during the Avamar Client for HP-UX installation. You must install the Avamar Plug-in for DB2 by using the `-x ask=true` option with the `swinstall` command.

Ensure that you install the Avamar Plug-in for DB2 in the same directory as Avamar Client for HP-UX.

Procedure

1. Log in to the DB2 server as root.
2. Change the directory to the temporary directory by typing the following command:

```
cd /tmp
```

where `tmp` is the temporary directory.

3. To install the Avamar Plug-in for DB2 in the default directory, type the following command:

```
swinstall -s AvamarDB2-platform-version.depot \*
```

where:

- *platform* is the HP-UX platform type.
- *version* is the Avamar software version.

4. To install the Avamar Plug-in for DB2 in an alternate directory:
 - a. Type the `swinstall` command:

```
swinstall -x ask=true -s /tmp/AvamarDB2-platform-version.depot  
hpuxavdb2,l=/install_path
```

where:

- *platform* is the HP-UX platform type.
 - *version* is the Avamar software version.
 - *install_path* is the installation directory.
- b. Type the name of the directory to use for the installation.
- The following output appears in the command shell:
- ```
Confirm '/install_path/' is the desired location. [n]
```
- c. Type **y** to confirm the location.

## Upgrading the Avamar Plug-in for DB2 on HP-UX

You must complete the required steps to upgrade the Avamar Plug-in for DB2 on HP-UX. The version of the Avamar Client for HP-UX and Avamar Plug-in for DB2 must be the same version.

### Procedure

1. Uninstall the Avamar Plug-in for DB2. [Uninstalling the Avamar Plug-in for DB2 on HP-UX on page 26](#) provides instructions.
2. Uninstall the Avamar Client for HP-UX. The *EMC Avamar Backup Clients User Guide* provides instructions.
3. Download and install the new version of the Avamar Client for HP-UX. The *EMC Avamar Backup Clients User Guide* provides instructions.
4. Download the Avamar Plug-in for DB2 installation package. [Downloading the software on page 24](#) provides instructions.
5. Install the new version of the Avamar Plug-in for DB2. [Installing the Avamar Plug-in for DB2 on HP-UX on page 25](#) provides instructions.

## Uninstalling the Avamar Plug-in for DB2 on HP-UX

You can uninstall the Avamar Plug-in for DB2 from an HP-UX system by using the `swremove` command.

When you uninstall the Avamar Plug-in for DB2 and the Avamar Client for HP-UX from the host system, scheduled backups no longer occur for the client. You cannot restore backups to the client after you uninstall the software.

You can retire or delete a client either before or after you uninstall the Avamar Plug-in for DB2:

- To keep the backups for the client so that you can restore the backups to a different client, retire the client by using Avamar Administrator.
- To delete the backups for the client, delete the client by using Avamar Administrator.

The *EMC Avamar Administration Guide* provides more information.

### Procedure

1. Log in to the DB2 server as root.
2. Uninstall the Avamar Plug-in for DB2 by typing the following command:

```
swremove hpuxavdb2
```

# Installing, upgrading, and uninstalling on IBM AIX

You can install, upgrade, and uninstall the Avamar Plug-in for DB2 on IBM AIX.

## Installing the Avamar Plug-in for DB2 on IBM AIX

You can install the Avamar Client for AIX software in either the default installation directory or an alternate directory. Use the `geninstall` command to install the Avamar Plug-in for DB2 in the default `var` directory or use the `installp` command to install the Avamar Plug-in for DB2 in a new location

Ensure that you install the Avamar Plug-in for DB2 in the same directory as Avamar Client for AIX. The installation returns an error if you try to install the Avamar Plug-in for DB2 in the default directory after you install the Avamar Client for AIX in an alternate directory.

### Procedure

1. Log in to the DB2 server as root.
2. Change the directory to the temporary directory by typing the following command:

```
cd /tmp
```

where *tmp* is the temporary install directory.

3. To install the Avamar Plug-in for DB2 in the default directory, type the following command:

```
geninstall -d AvamarDB2-aix6-ppc64-version.bff all
```

where *version* is the Avamar software version.

4. To install the Avamar Plug-in for DB2 in an alternate directory, type the following command:

```
installp -R /install_path -d AvamarDB2-aix6-ppc64-version.bff all
```

where:

- *install\_path* is the directory for the installation files.
- *version* is the Avamar software version.

## Upgrading the Avamar Plug-in for DB2 on IBM AIX

Use the `geninstall` command to upgrade the software in the default directory or use the `installp` command to upgrade the software in an alternate directory. You must upgrade the Avamar Plug-in for DB2 before you upgrade the Avamar Client for AIX. The versions of the Avamar Client for AIX and Avamar Plug-in for DB2 must be the same.

### Procedure

1. Download the Avamar Plug-in for DB2 installation package. [Downloading the software on page 24](#) provides instructions.
2. Log in to the DB2 server as root.
3. Change the directory to the temporary directory by typing the following command:

```
cd /tmp
```

where *tmp* is the temporary install directory.

4. To upgrade the Avamar Plug-in for DB2 in the default directory, type the following command:

```
geninstall -d AvamarDB2-aix6-ppc64-version.bff all
```

where *version* is the Avamar software version.

5. To upgrade the Avamar Plug-in for DB2 in an alternate directory, type the following command:

```
installp -R /install_path -d AvamarDB2-aix6-ppc64-version.bff all
```

where:

- *install\_path* is the directory for the installation files.
- *version* is the Avamar software version.

6. Download the Avamar Client for AIX. The *EMC Avamar Backup Clients User Guide* provides instructions.

7. To upgrade the Avamar Client for AIX in the default directory, type the following command:

```
geninstall -d AvamarClient-aix6-ppc-version.bff all
```

where *version* is the Avamar software version.

8. To upgrade the Avamar Client for AIX in an alternate installation directory, type the following command:

```
installp -R /install_path -d AvamarClient-aix6-ppc-version.bff all
```

where:

- *install\_path* is the directory for the installation files.
- *version* is the Avamar software version.

## Uninstalling the Avamar Plug-in for DB2 on IBM AIX

You can uninstall the Avamar Plug-in for DB2 from an IBM AIX system by using the `geninstall` or `installp` command. Use the `geninstall` command to uninstall the software in the default directory or use the `installp` command to uninstall the software in an alternate directory.

When you uninstall the Avamar Plug-in for DB2 and the Avamar Client for AIX from the host system, scheduled backups no longer occur for the client. You cannot restore backups to the client after you uninstall the software.

You can retire or delete a client either before or after you uninstall the Avamar Plug-in for DB2.

- To keep the backups for the client so that you can restore the backups to a different client, retire the client by using Avamar Administrator.
- To delete the backups for the client, delete the client by using Avamar Administrator.

The *EMC Avamar Administration Guide* provides more information.

### Procedure

1. Log in to the DB2 server host as root.
2. View all Avamar packages installed on the system by typing the following command:

```
lsllpp -l | grep Avamar
```

The following output appears in the command shell:

```
AvamarClient-aix6-ppc VERSION COMMITTED EMC Avamar client
VERSION
AvamarDB2-aix6-ppc64 VERSION COMMITTED EMC Avamar client
VERSION
```

3. To uninstall the Avamar Plug-in for DB2 software in the default directory, type the following command:

```
geninstall -u AvamarDB2-aix6-ppc64
```

4. To uninstall the Avamar Plug-in for DB2 software in an alternate directory, type the following command:

```
installp -R /install_path -u AvamarDB2-aix6-ppc
```

where *install\_path* is the directory for the installation files.

5. Uninstall the Avamar Client for AIX software by typing the following command:

```
geninstall -u AvamarClient-aix6-ppc
```

## Installing, upgrading, and uninstalling on Linux

You can install, upgrade, and uninstall the Avamar Plug-in for DB2 on Linux.

### Installing the Avamar Plug-in for DB2 on Linux

You can install the Avamar Plug-in for DB2 software in either the default installation directory or an alternate directory by using the `rpm` command.

Ensure that you install the Avamar Plug-in for DB2 in the same directory as the Avamar Client for Linux.

#### Procedure

1. Log in to the DB2 server as root.
2. Change the directory to the temporary directory by typing the following command:

```
cd /tmp
```

where *tmp* is the temporary install directory.

3. To install the software in the default directory, type the following command:

```
rpm -ivh AvamarDB2-linux-platform-version.rpm
```

where:

- *platform* is the Linux platform type.
- *version* is the Avamar software version.

4. To install the software in an alternate directory, type the following command:

```
rpm --relocate /usr/local/avamar=/install_path -ivh AvamarDB2-
linux-platform-version.rpm
```

where:

- *install\_path* is the directory where you installed the Avamar Client for Linux.
- *platform* is the Linux platform type.

- *version* is the Avamar software version.

## Upgrading the Avamar Plug-in for DB2 on Linux

Use the `rpm` command to upgrade the software in the default directory or the `rpm` command with the `--relocate` option to upgrade the software in an alternate directory. The versions of the Avamar Client for Linux and Avamar Plug-in for DB2 must be the same.

### Procedure

1. To upgrade the Avamar Client for Linux, use the instructions in the *EMC Avamar Backup Clients User Guide*.

2. To upgrade the software in the default directory, type the following command:

```
rpm -Uvh AvamarDB2-linux-platform-version.rpm
```

where:

- *platform* is the Linux platform type.
- *version* is the Avamar software version.

3. To upgrade the software in an alternate directory, type the following command:

```
rpm -Uvh --relocate /usr/local/avamar=install_path AvamarDB2-linux-platform-version.rpm
```

where:

- *install\_path* is the directory where you installed the Avamar Client for Linux.
- *platform* is the Linux platform type.
- *version* is the Avamar software version.

## Uninstalling the Avamar Plug-in for DB2 on Linux

You can uninstall the Avamar Plug-in for DB2 from a Linux system by using the `rpm -e` command.

When you uninstall the Avamar Plug-in for DB2 and the Avamar Client for Linux from the host system, scheduled backups no longer occur for the client. You cannot restore backups to the client after you uninstall the software.

You can retire or delete a client either before or after you uninstall the Avamar Plug-in for DB2.

- To keep the backups for the client so that you can restore the backups to a different client, retire the client by using Avamar Administrator.
- To delete the backups for the client, delete the client by using Avamar Administrator.

The *EMC Avamar Administration Guide* provides more information.

### Procedure

1. Log in to the DB2 server host as root.
2. List the Avamar software installed on the system by typing the following command:

```
rpm -qa | grep Av
```

A list of Avamar software appears in the command shell:

```
AvamarClient-version
AvamarDB2-version
```

3. Uninstall the Avamar Plug-in for DB2 by typing the following command:

```
rpm -e AvamarDB2-version
```

where *AvamarDB2-version* is the Avamar Plug-in for DB2 installation package.

4. Uninstall the Avamar Client for Linux by typing the following command:

```
rpm -e AvamarClient-version
```

where *AvamarClient-version* is the Avamar software installation package.

## Installing, upgrading, and uninstalling on Solaris

You can install, upgrade, and uninstall the Avamar Plug-in for DB2 on Solaris.

### Installing the Avamar Plug-in for DB2 on Solaris

You can install the Avamar Client for Solaris software by using the `pkgadd` command.

Ensure that you install the Avamar Plug-in for DB2 in the same directory as the Avamar Client for Solaris.

#### Procedure

1. Log in to the DB2 server as root.
2. Change the directory to the temporary directory by typing the following command:

```
cd /tmp
```

where *tmp* is the temporary install directory.

3. Install the software by typing the following command:

```
pkgadd -d AvamarDB2-solaris10-platform-version.pkg
```

where *platform-version* is the platform type and Avamar version number.

The following output appears in the command shell:

```
The following packages are available:
1 AVMRdb2 Avamar Client Plugin for DB2
(sparc) 7.2.100-nnn
Select package(s) you wish to process (or 'all' to process
all packages). (default: all) [?,??,q]:
```

4. Type **1** and press **Enter**.

The following output appears in the command shell:

```
Processing package instance <AVMRdb2> from
</tmp/AvamarDB2-solaris10-sparc-7.2.100-nnn.pkg>
```

```
Avamar Client Plugin for DB2(sparc) 7.2.100-nnn
Relocate install from /opt/AVMRclnt? [n]
```

5. Press **Enter** to accept the default install location.

The following output appears in the command shell:

```
Executing checkinstall script.
Using as the package base directory.
```

```

Processing package information.
Processing system information.
Verifying package dependencies.
Verifying disk space requirements.
Checking for conflicts with packages already installed.
Checking for setuid/setgid programs.
This package contains scripts which will be executed with
super-user permission during the process of installing this
package.
Do you want to continue with the installation of <AVMRdb2>
[y,n,?]

```

6. Type **y** and press **Enter**.

The following output appears in the command shell:

```

Executing checkinstall script.
Using as the package base directory.
Processing package information.
Processing system information.
3 package pathnames are already properly installed.
Verifying package dependencies.
Verifying disk space requirements.
Checking for conflicts with packages already installed.
The following files are already installed on the system and
are being used by another package: /opt/AVMRclnt/lib/
libgcc_s.so.1
Do you want to install these conflicting files [y,n,?,q]

```

7. Type **y** and press **Enter**.

The following output appears in the command shell:

```

Checking for setuid/setgid programs.
This package contains scripts which will be executed with
super-user
permission during the process of installing this package.
Do you want to continue with the installation of <AVMRdb2>
[y,n,?]

```

8. Type **y** and press **Enter**.

The installation runs to completion.

## Upgrading the Avamar Plug-in for DB2 on Solaris

You must complete the required steps to upgrade the Avamar Plug-in for DB2 on a Solaris system. The versions of the Avamar Client for Solaris and Avamar Plug-in for DB2 must be the same.

### Procedure

1. Uninstall the Avamar Plug-in for DB2. [Uninstalling the Avamar Plug-in for DB2 on Solaris on page 33](#) provides instructions.
2. Uninstall the Avamar Client for Solaris. The *EMC Avamar Backup Clients User Guide* provides instructions.
3. Download the Avamar Plug-in for DB2 installation package. [Downloading the software on page 24](#) provides instructions.
4. Download and install the new version of the Avamar Client for Solaris. The *EMC Avamar Backup Clients User Guide* provides instructions.



5. Install the new version of the Avamar Plug-in for DB2. [Installing the Avamar Plug-in for DB2 on Solaris on page 31](#) provides instructions.

## Uninstalling the Avamar Plug-in for DB2 on Solaris

You can uninstall the Avamar Plug-in for DB2 from a Solaris system by using the `pkgrm` command.

When you uninstall the Avamar Plug-in for DB2 and the Avamar Client for Solaris from the host system, scheduled backups no longer occur for the client. You cannot restore backups to the client after you uninstall the software.

You can retire or delete a client either before or after you uninstall the Avamar Plug-in for DB2.

- To keep the backups for the client so that you can restore the backups to a different client, retire the client by using Avamar Administrator.
- To delete the backups for the client, delete the client by using Avamar Administrator.

The *EMC Avamar Administration Guide* provides more information.

### Procedure

1. Log in to the DB2 server host as root.
2. Display all Avamar packages installed on the system by typing the following command:

```
pkginfo | grep AVMR
```

Information similar to the following appears in the command shell:

```
The following packages are currently installed:
1 AVMRclnt Avamar Client
(sparc) 7.2.100-nnn
2 AVMRdb2 Avamar Client Plugin for DB2
(sparc) 7.2.100-nnn
```

3. Note the package names.
4. Uninstall the software by typing the following command:

```
pkgrm package_name
```

where *package\_name* is the Avamar plug-in package.

The following output appears in the command shell:

```
The following package is currently installed:
package_name
Do you want to remove this package?
```

5. Type **y** and press **Enter**.

The following output appears in the command shell:

```
Removal of package_name was successful.
```

## Installing, upgrading, and uninstalling on Windows

You can install, upgrade, and uninstall the Avamar Plug-in for DB2 on Windows.

## Installing the Avamar Plug-in for DB2 on Windows

You can install the Avamar Client for Windows software in either the default installation directory or an alternate directory. The installation process automatically installs the Avamar Plug-in for DB2 in the same directory as the Avamar Client for Windows.

If UAC is enabled on the client computer, you must start the setup wizard by using administrator privileges. Otherwise, the software does not install correctly. This procedure provides one method to bypass UAC. The Microsoft documentation provides other methods and additional information.

### Procedure

1. Log in to the DB2 server as an administrator.
2. Go to the temporary directory that contains the installation package that you downloaded in [Downloading the software on page 24](#).
3. Start the Avamar Plug-in for DB2 installation by using the correct method:
  - If UAC is disabled, double-click the installation package.
  - If UAC is enabled, right-click the **Command Prompt** icon and select **Run as administrator**. Change to the directory to the directory that contains the installation package and type the following command:

```
msiexec /I AvamarDB2-windows-platform-version.msi
```

where:

- *platform* is the Windows platform type.
- *version* is the Avamar software version.

The welcome page appears.

4. Click **Next**.

The **Ready to Install EMC Avamar Plug-in for DB2** page appears.

5. Click **Install**.

The **Installing EMC Avamar Backup Plug-in for DB2** page appears. A status bar shows the installation's progress. After the installation completes, the **Completed the EMC Avamar Backup Plug-in for DB2 Setup Wizard** page appears.

6. Click **Finish**.

## Upgrading the Avamar Plug-in for DB2 on Windows

When you upgrade the Avamar Plug-in for DB2, you do not need to uninstall earlier versions before you install a new version. The installation determines that an earlier version is installed, and then prompts you to upgrade to the new version or remove the current version.

### Procedure

1. Ensure that you meet all system requirements for the new version. [Preparing to install the Avamar Plug-in for DB2 on page 24](#) provides information.
2. Upgrade the Avamar Client for Windows by running the Windows client installation wizard for the new version on the client computer. The *EMC Avamar for Windows Server User Guide* provides instructions.

3. Upgrade the Avamar Plug-in for DB2 by running the plug-in installation wizard for the new version on the Windows server. [Installing the Avamar Plug-in for DB2 on Windows on page 34](#) provides instructions.

## Uninstalling the Avamar Plug-in for DB2 on Windows

When you uninstall the Avamar Plug-in for DB2 and the Avamar Client for Windows from the host system, scheduled backups no longer occur for the client. You cannot restore backups to the client after you uninstall the software.

You can retire or delete a client either before or after you uninstall the Avamar Plug-in for DB2.

- To keep the backups for the client so that you can restore the backups to a different client, retire the client by using Avamar Administrator.
- To delete the backups for the client, delete the client by using Avamar Administrator.

The *EMC Avamar Administration Guide* provides more information.

### Procedure

1. Uninstall the Avamar Plug-in for DB2 by using **Programs and Features**.
2. Uninstall the Avamar Client for Windows by using **Programs and Features**.



# CHAPTER 3

## Backup

This chapter includes the following topics:

- [Preparing the database for backup](#).....38
- [Preparing for DPF backups](#).....40
- [Performing on-demand backups](#).....41
- [Scheduling backups](#).....43
- [Monitoring backups](#)..... 47
- [Canceling backups](#).....48

## Preparing the database for backup

Before you use the Avamar Plug-in for DB2 to perform backups, you must configure the database appropriately.

### Configuring automatic backups for DB2 transaction logs

You can configure the DB2 database to enable automatic backups of transaction logs.

DB2 uses the `LOGARCHMETH1` and `LOGARCHOPT1` parameters to enable automatic backups of a transaction log as soon as it is archived. DB2 10.1 includes a new parameter, `LOGARCHCOMPR1`, to enable archive log compression. Leave this parameter set to its default value, off. Avamar performs its own compression.

#### Procedure

1. Create the Avamar Plug-in for DB2 flag file. [Creating the Avamar Plug-in for DB2 flag file on page 38](#) provides instructions.
2. Configure the database for log backups by typing the following command:

```
db2 update db cfg for database_name using logarchmeth1
VENDOR:vendor_library logarchopt1 @pathname
```

where:

- *database\_name* is the name of the database to back up.
- *vendor\_library* is the full pathname to the shared library of the Avamar Plug-in for DB2.
- *pathname* is the absolute pathname to the flag file that you created in [step 1 on page 38](#).

### Creating the Avamar Plug-in for DB2 flag file

Before you back up DB2 data, create a flag file. You can choose any name for the flag file; for example, `avdb2.flg`. Specify the Avamar server user credentials and other parameters in the flag file. To perform log backups, the Avamar Plug-in for DB2 requires you to set Avamar server user credentials in the flag file.

#### Procedure

1. Create a text file.
2. Type the required information in the text file. The following file is an example flag file:

```
--id=user-1@/clients/hostA.avamar.emc
--password=obfuscated password
--sysdir=c:\Progra~1\avs\etc
--dbpartitionnums=0,1,2,3
--catnode=0
--logfile=e:\avdb2-cli.log
--labelnum=256
--ddr=true
--ddr-index=1
```

where:

- `--id`, `--password`, and `--sysdir` are mandatory.

- `--dbpartitionnums` specifies the list of partitions for a single-system view.  
The `--dbpartitionnums` flag is mandatory for DPF configurations.
- `--catnode` specifies the partition number of the catalog node.  
The `--catnode` flag is mandatory for DPF configurations.
- `--logfile` is optional.
- `--labelnum` is mandatory to restore backups from Avamar releases before 7.0.
- `--ddr` and `--ddr-index` are mandatory for backups to Data Domain systems.

---

#### Note

The `--id` and `--password` parameters are not necessary for database backups if you include them in the `avdb2.cmd` file.

---

3. Save the text file and ensure the mode of the file is set properly for DB2-user read permission.

## Performing offline backups

DB2 databases must not have any application connections when you perform an offline backup.

### Procedure

1. Ensure that no clients connect to the database during the backup operation.
2. Ensure that no changes to the database are taking place during the backup window.

A database modification during a backup can cause the backup to fail.

## Performing online backups

The Avamar Plug-in for DB2 supports setting up log archiving only with the `LOGRETAIN` and `VENDOR` parameters. Before you perform the first online backup, enable archiving logging by configuring the `LOGRETAIN` and `VENDOR` parameters.

### Procedure

1. For DB2 version 9.1 and earlier, to use the `LOGRETAIN` parameter, type the following command:

```
db2 update db cfg for database_name using LOGRETAIN ON
```

where *database\_name* is the name of the database to back up.

2. For DB2 version 9.5 and later, to use the `LOGRETAIN` parameter, type the following commands:

```
update db cfg for database_name using LOGARCHMETH1 LOGRETAIN
update db cfg for database_name using LOGARCHMETH1 DISK
```

where *database\_name* is the name of the database to back up.

3. To use the `VENDOR` parameter, use the `db2 update db cfg` command in [Configuring automatic backups for DB2 transaction logs on page 38](#).

4. You must also select the **Create an online backup** option for the dataset or for an on-demand backup.

## Preparing for DPF backups

In a DPF environment, you can back up individual partitions in a database or select the catalog node to back up a combination of partitions or all partitions.

## Configuring the backup agent for DPF backups

Before you back up a DB2 database partition, you must configure the **Backup agent** service on all Windows systems in the DPF environment to use the domain administrator account.

### Procedure

1. From the Windows **Start** menu, select **Run**.  
The **Run** dialog box appears.
2. Type **services.msc** in the **Open** field.  
The **Services** window appears.
3. Configure the **Backup agent** service:
  - a. Right-click **Backup agent**, and then select **Properties**.  
The **Backup agent Properties** dialog box appears.
  - b. Click the **Log On** tab, and then select **This account**.
  - c. Click **Browse**.  
The **Select User** dialog box appears.
  - d. Select the domain administrator account, and then click **OK**.
  - e. Click **OK** to close the **Backup agent Properties** dialog box.
4. In the **Services** window, right-click **Backup agent** and select **Restart**.

## DPF backup limitations

Backups of database partition can fail when you perform a backup from a non-catalog node.

You cannot perform a database partition backup from a non-catalog node. Doing so returns the following error:

```
Cannot perform multi-partition backup.
The catalog node for the database is not present on this
server.
```

You cannot back up a node in a multi-partition configuration unless all nodes are online. A multi-partition backup fails if one or more nodes is offline. The backup returns the following error messages for this type of failure:

```
2012/4/1-13:14:07.21048 [avdb2ctlplugin_assist] snapup: return
from db2 API
2012-4-1 18:44:07 avdb2 Error <0000>: snapup: failed to create
backup of database [db2inst1/AVAMAR2]. db2 errcode -1170
2012-4-1 18:44:07 avdb2 Error <9018>: DB2 returned error -1170
```



```
2012/4/1-13:14:07.21122 [avdb2ctlplugin_assist] retire_manager:
force terminate
```

## Performing on-demand backups

An on-demand backup is a user-initiated backup of specific data that you select. Perform an on-demand backup for the first backup of the client immediately after you install the Avamar client software. You should also perform an on-demand backup before system maintenance, software installations, or software upgrades.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Backup** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

A list of Avamar clients appears in the pane under the domains list.

4. Select the host of the DB2 server, the host of a DPF node, or the DPF catalog node.

In a DPF environment, select the host of a DPF node to back up individual partitions in a database, or select the catalog node to back up a combination of partitions or all partitions.

The **Browse Command Line Options** dialog box appears.

5. In the **Browse Command Line Options** dialog box, type the DB2 instance credentials:

- a. Type the name of the DB2 instance to browse in the **DB2 Instance Name** field.
- b. Type the instance owner or system admin username in the **Instance Admin Username** field.
- c. Type the password for the username in the **Instance Admin Password** field.
- d. Click **OK**.

DB2 instance folders appear.

6. Click the DB2 instance folder, and then select the instance folder, a single database, or multiple databases.

7. Select **Actions > Back Up Now**.

The **On Demand Backup Options** dialog box appears.

8. Select a retention policy:
  - To automatically delete this backup from the Avamar server after a specific amount of time, select **Retention period** and specify the number of days, weeks, months, or years for the retention period.
  - To automatically delete this backup from the Avamar server on a specific calendar date, select **End date** and browse to that date on the calendar.
  - To keep this backup for as long as this client remains active in the Avamar server, select **No end date**.
9. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during the backup.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

10. Click **More Options**.

The **Backup Command Line Options** dialog box appears.

11. Set the plug-in options:

- a. Select **Create an online backup** to perform an online backup.
- b. Select **Exclude archive logs in online backup** to exclude archive logs from an online backup.  
  
If you exclude archive logs from the database backup, ensure that archive log files are included in file system backups. Failure to do so might result in loss of data.
- c. Select **Optimize backup deduplication** to enable the DB2 `dedup_device` option for the backup.

---

**Note**

Only specific DB2 versions support the DB2 `dedup_device` option. Check the IBM documentation to determine if the DB2 version supports the `dedup_device` option. A backup fails if you select the **Optimized backup deduplication** option for a backup of a DB2 database that does not support the `dedup_device` option.

---

- d. Type the instance owner or system admin username in the **Instance Admin Username** field.
- e. Type the password for the username in the **Instance Admin Password** field.
- f. Specify the partitions to include in the backup in the **Database Partition Numbers** field:
  - To specify all database partitions, type **ALL** or **a11**. Specifying all partitions numerically is not the same as using **ALL** or **a11**.
  - To specify a list of partitions, type the partition numbers in a comma-separated list. For a single partition setup, leave this field blank.
- g. Select the number of sessions to use for the backup from the **Number of sessions during backup** list.
- h. Select **Store backup on Data Domain** system to store the backup on a Data Domain system instead of the Avamar server, and then select the Data Domain system from the list.
- i. From the **Encryption method to Data Domain system** list, select the encryption method to use for data transfer between the client and the Data Domain system during the backup.

12. Click **OK** to return to the **On Demand Backup Options** dialog box.

13. Click **OK** again.

The **On Demand Backup Options** dialog box closes and the backup begins.

14. Select **Actions > View Activity** to view status details for the backup. [Monitoring backups on page 47](#) provides more information about viewing backups.

## Scheduling backups

Scheduled backups run automatically to ensure that backups of the DB2 data occur on an ongoing basis. You can schedule backups to run daily, weekly, or monthly. The scheduled backup can include multiple clients or a single server.

### Procedure

1. Create a dataset for the backups.
2. Create a group for the backups.

During the group creation process, you:

- a. Assign the new dataset to the new group.
- b. Assign a schedule to the new group.
- c. Assign a retention policy to the new group.
- d. Add one or more clients to the new group.

The *EMC Avamar Administration Guide* provides more information about groups, group policy, datasets, schedules, and retention policies.

3. Enable scheduling for the group.

## Creating a dataset

A dataset specifies the data to include in a scheduled backup and the options to use for the backup. Create at least one dataset for scheduled backups on a client or group of clients. Create multiple datasets to segregate client data.

### Procedure

1. In Avamar Administrator, select **Tools > Manage Datasets**.

The **Manage All Datasets** window appears.

2. Click **New**.

The **New Dataset** dialog box appears.

3. In the **Name** box, type a name for the dataset.

The name can include alphanumeric characters (A-Z, a-z, 0-9) and the following special characters: period (.), hyphen (-), and underscore (\_). Do not use Unicode characters or the following special characters: ` ~ ! @ # \$ % ^ & \* ( ) = + [ ] { } | \ / ; : ' " < > , ?

4. On the **Source Data** tab, select **Enter Explicitly**.
5. Select the DB2 plug-in for the platform from the **Select Plug-In Type** list.
6. Click ... (the **Browse for files and/or folder** button).

The **Select Files and/or Folders** dialog box appears.

7. Set the options in the **Select Files and/or Folder** dialog box:

- a. In the **Clients** tree, browse to the host of the DB2 server.

The Avamar clients and plug-ins installed on the client appear in the middle pane.

- b. Select the DB2 plug-in for the platform type.

The **Browse Command Line Options** dialog box appears.

- c. Type the name of the DB2 instance to browse in the **DB2 Instance Name** field.
  - d. Type the instance owner or system admin username in the **Instance Admin Username** field.
  - e. Type the password for the username in the **Instance Admin Password** field.
  - f. Click **OK**.  
DB2 instance folders appear.
  - g. Select the database to include in the dataset.
  - h. Click **OK**.  
The **Select Files and /or Folder** dialog box closes and the **New Dataset** dialog box lists the files or folders that you selected.
8. Remove all entries from the source list other than the DB2 files that you selected:
    - a. Select an entry from the list.
    - b. Click **-**.
    - c. Repeat steps a and b to remove all other entries other than the DB2 files that you selected.
  9. Leave **Inclusion** and **Exclusion** tabs as they are. The Avamar Plug-in for DB2 does not support include or exclude lists.
  10. Click the **Options** tab and set the plug-in options:
    - a. Select **Create an online backup** to perform an online backup.
    - b. Select **Exclude archive logs in online backup** to exclude archive logs from an online backup.
    - c. Select **Optimize backup deduplication** to enable the DB2 dedup\_device option for this backup.

---

**Note**

Only specific DB2 versions support the dedup\_device option. Check the vendor documentation to determine if the DB2 version supports the dedup\_device option. A backup fails if you select the **Optimized backup deduplication** option for a backup of a DB2 database that does not support the dedup\_device option.

---


- d. Type the instance owner or system admin username in the **Instance Admin Username** field.
- e. Type the password for the username in the **Instance Admin Password** field.
- f. Specify the partitions to include in the backup in the **Database Partition Numbers** field:
  - To specify all database partitions, type **ALL** or **a11**. Specifying all partitions numerically is not the same as using **ALL** or **a11**.
  - To specify a list of partitions, type the partition numbers in a comma-separated list. For a single partition setup, leave this field blank.
- g. Select the number of sessions to use for the backup from the **Number of sessions during backup** list.

[Concurrent backups and restores on page 20](#) provides more information about how Avamar Plug-in for DB2 handles multiple backup sessions.

- h. Select **Store backup on Data Domain system** to store the backup on a Data Domain system instead of the Avamar server.
- i. From the **Encryption method to Data Domain system** list, select the encryption method to use for data transfer between the client and the Data Domain system during the backup.

11. Click **OK**.

The new dataset appears in the list of datasets.



The <browse> flags that appear under **Options** in the **Manage All Datasets** dialog box also appear in the output of the corresponding `mccli dataset show --domain --name` command. For example:

```
./mccli dataset show --domain=/JT --name=tmp01
```

```
0,23000,CLI command completed successfully.
Attribute Value

Name tmp01
ID 1361306652681
Domain /JT
Built-in false
ALLDATA false
Num Targets 1
Linux DB2 Target jt971/TMP01
Linux DB2 Target ID 1009
Num Includes 0
Num Excludes 0
Num Flags 12
Linux DB2 Flag type=string:name<browse>=db2_inst_name:value=jt971
Linux DB2 Flag type=string:name<browse>=db2_inst_user:value=jt971
Linux DB2 Flag type=string:name=db2_inst_user:value=bk-jt971
Linux DB2 Flag type=checkbox:name=ddr:value=false
Linux DB2 Flag type=pulldown:name=ddr-index:value=0
Linux DB2 Flag type=checkbox:name=debug:value=false
Linux DB2 Flag type=password:name<browse>=inst_admin_password:value=*
```

```

LINUX DB2 Flag type=password:name=inst_admin_password:value=*
LINUX DB2 Flag type=pulldown:name=max-streams:value=1
LINUX DB2 Flag type=checkbox:name=nologs:value=false
LINUX DB2 Flag type=checkbox:name=online:value=false
LINUX DB2 Flag type=checkbox:name=optimize-dedup:value=false
Is Link false

```

## Creating a group

When you create a group, you define the dataset, schedule, and retention policy, which together comprise the group policy for scheduled backups of all members of the group. A group must contain at least one Avamar client. When the group contains two or more clients, the clients must belong to the same Avamar domain. You can override group policy settings at the client level.

You cannot edit schedules or retention policies when you use the **New Group** wizard to create a group. Review existing schedules and retention policies. If required, create new ones before you create a group. The *EMC Avamar Administration Guide* provides information about editing schedule properties and retention policies.

### Procedure

1. In Avamar Administrator, click the **Policy** launcher button.

The **Policy** window appears.

2. Click the **Policy Management** tab.
3. Select the **Groups** tab.

The **Policy** window displays a table that contains groups for the domain.

4. Select the domain for the DB2 server.
5. Select **Actions > Group > New > Backup Group**.

The **New Group** page appears.

6. Type a name for the new group in the **Name** box.

The name can include alphanumeric characters (A-Z, a-z, 0-9) and the following special characters: period (.), hyphen (-), and underscore (\_). Do not use Unicode characters or the following special characters: ` ~ ! @ # \$ % ^ & \* ( ) = + [ ] { } | \ / ; : ' " < > , ?

7. Clear the **Disabled** checkbox to use this group for scheduled client backups.

Selecting the checkbox disables backups for the group.

8. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during the backup.

The encryption technology and bit strength for the client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides additional information.

9. (Optional) Select **Override Schedule** to override the assigned schedule for this group:

- To skip the next scheduled backup, select **Skip Next Backup**.
- To perform the next scheduled backup one time only, select **Run Next Backup Once**.

10. Click **Next**.

The next **New Group** page appears with dataset information.

11. Select the dataset that you created from the **Select an Existing Dataset** list, and then click **Next**.

The next **New Group** page appears with schedule information.

12. Select a schedule from the **Select an Existing Schedule** list, and then click **Next**.

The next **New Group** page appears with retention policy information.

13. Select a retention policy from the **Select an Existing Retention Policy** list, and then click **Next**.

The final **New Group** page appears with a list of domains in the **Choose Domain** pane.

14. Select the domain that contains the DB2 server.

A list of Avamar clients appears in the pane under the **Choose Domain** pane.

15. Select the checkbox next to the clients to include in the group. You can select the **Client** checkbox to include all clients.

The clients you select appear in the **Members** pane.

16. (Optional) To remove a client from the group, select the client from the **Members** list, and then click the red X.

17. Click **Finish**.

The **New Group** wizard closes and the new group appears in the table in the **Policy** window.

## Enabling scheduled backups

Scheduled backups occur only for enabled groups. Groups are disabled by default unless you select the **Enabled** checkbox on the first page of the **New Group** wizard. If you did not enable the group when you created it, use the menu options in the **Policy** window to enable backups.

### Procedure

1. In Avamar Administrator, click the **Policy** launcher tab.

The **Policy** window appears.

2. Click the **Policy Management** tab.
3. Click the **Groups** tab.
4. Select the domain for the DB2 server.
5. Select the group that you created.
6. Enable the group, if required by selecting **Actions > Group > Disable Group**.

Perform this step only if a check mark appears next to the **Disable Group** menu option.

7. Click **Yes** to enable this group.

## Monitoring backups

You can monitor backups to ensure that the backups complete successfully and to troubleshoot issues. The **Activity Monitor** in Avamar Administrator enables you to view status information for both on-demand and scheduled backups.

### Procedure

1. In Avamar Administrator, click the **Activity** launcher button.

The **Activity** window appears.

2. Click the **Activity Monitor** tab.

A list of all activities appears.

3. To filter the results to display only backup activity, select **Actions › Filter**.  
The **Filter Activity** dialog box appears.
4. Select **All Backups** from the **Type** list.
5. Click **OK**.

## Canceling backups

You can cancel a backup at any time before it completes. The cancellation process can take five minutes or more. The backup might complete before the cancellation process finishes.

### Procedure

1. In Avamar Administrator, click the **Activity** launcher button.  
The **Activity** window appears.
2. Click the **Activity Monitor** tab.  
A list of all activities appears.
3. Select the backup from the list.
4. Select **Actions › Cancel Activity**.  
A confirmation message appears.
5. Click **Yes**.



# CHAPTER 4

## Restore and Recovery

This chapter includes the following topics:

|                                                                |    |
|----------------------------------------------------------------|----|
| • Backup naming conventions.....                               | 50 |
| • Restoring DB2 databases to the original location.....        | 51 |
| • Restoring DB2 databases to a different client.....           | 63 |
| • Restoring and recovering DPF.....                            | 68 |
| • Restoring table spaces in a stand-alone DB2 environment..... | 75 |
| • Restoring table spaces in a DB2 DPF environment.....         | 79 |
| • Recovering retired clients.....                              | 82 |
| • Disaster recovery.....                                       | 84 |


## Backup naming conventions

The naming convention that the Avamar Plug-in for DB2 uses is based on the standard naming convention that DB2 uses.

The **Backup, Restore and Manage** window in Avamar Administrator displays backup label and backup image names for backups available to restore. Backup labels appear to the right of the calendar in the **Backups** table. Backup image names appear below the **Backups** table in the **Contents of Backup** table.

The following figure shows the label name and image name for a backup that a user selects for restore.

**Figure 2** Backup label and image names



## Backup labels and image names for a database backup

Backup labels for database backups contain specific elements. A backup label, for example, contains an element that shows you whether the CLI or GUI was used to create the backup.

Backup labels for database backups use the following naming convention:

*interface-database\_status-backup\_type*

where:

- *interface* is CLI or GUI.
- *database\_status* is C for an offline database backup and H for an online database backup.

CLI-C-DB2 Databases (s) backup, for example, is the backup label that is selected in [Figure 2 on page 50](#).

Backup image names for database backups are specific to the version of DB2. Versions 9.5 and 9.7 use the following naming convention:

*db\_name.DB2\_backup\_type.instance\_name.node\_id.catalognode\_id.  
DB2\_backup\_timestamp.stream\_sequence\_number*

where the value of *DB2\_backup\_type* is 0, 3, or 4:

- 0 represents a full backup of a database.
- 3 represents a backup of a table space.
- 4 represents a backup image the `LOAD . . . COPY TO` command creates.

Backup image names in DB2 10 use a different naming convention. The *node\_id.catalognode\_id* format changes to *part\_id*.

---

#### Note

The Avamar image format for DB2 10 is the same as DB2 versions 9.7 and 9.5. The DB2 10 native format is different than DB2 9.7.

---

AVAMAR1.0.db2inst1.NODE0000.CATN0000.20121129175842.001, for example, is a backup image name. The 0 (zero) value for *DB2\_backup\_type* in this backup image name indicates that the image backup is a full backup of a database.

## Backup labels and image names for log backups

Backup labels for log backups contain specific elements. A backup label, for example, contains an element that shows you the sequence number of the log backup.

Backup labels for log backups use the following naming convention:

*db\_name-chain-number\_sequence-number.LOG*

AVAMAR1-C0000042\_S0000038.LOG is an example backup label name for a log backup.

Backup image names for log backups use the following naming convention:

*chain-number\_sequence-number.LOG*

C0000042\_S0000038.LOG is an example backup image name for a log backup.

The display for the directory structure that contains the log files shows the instance, the database, and the node for the log files.

The backup image name is the same for backups from Avamar Administrator and from the DB2 CLP.

## Restoring DB2 databases to the original location

You can restore DB2 databases to the original directory on the original client by using Avamar Administrator. The Avamar Plug-in for DB2 can restore offline backups, online backups that include archive log, online backups that do not include archive logs, and backups of archive logs.

### Restoring offline backups

You can restore an offline backup to the original directory. A backup label, for example, GUI-C-DB2 Database(s) backup contains a “C” in its name. The “C” indicates that the backup is for an offline database.

#### Before you begin

Ensure that the DB2 database is inactive. During the restore operation, do not connect to the database.

#### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

- Click the **Restore** tab.

The top-left pane contains a list of domains.

- Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

- Select the host of the DB2 server.

- Click the **By Date** tab.

- Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.


- Expand the DB2 instance folder.

- Select one or more database backups to restore.

#### Note

For DPF restore operations from Avamar Administrator, the Avamar Plug-in for DB2 limits the selection of DPF nodes to one node and one database.

The following figure shows the **Restore** tab in the **Backup, Restore and Manage** window after a database is selected.



- Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

10. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

11. Select **Restore everything to its original location**.

12. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

13. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select **Restore only**.

---

#### Note

Leave the **Recovery Type** panel as is. The **Recovery Type** options apply only to the **Restore and roll forward database** option and the **Recover** option.

---

- c. Select the number of sessions to use for the restore from the **Number of sessions** during restore list.

---

#### Note

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- d. Type the instance owner or system admin username in the **Instance Admin Username** field.
- e. Type the password for the username in the **Instance Admin Password** field.
- f. Leave the **Database Partition Numbers** field blank. This field only applies to DPF environments.
- g. Leave the **Directory Path to Restore Archive Logs** field blank. This field only applies to online backups that include archive logs.

A restore of an offline backup fails if the **Directory Path to Restore Archive Logs** field contains a pathname. The error message for this type of failure is similar to the following message:

```
restore: Invalid option for archive logs. Backup image
db2inst1/c-AVAMAR1-1-sles10-32-db2-95-dpf does not contain
archive logs
```

- h. Leave **Database Name** field blank. This field only applies to redirected restores.
- i. Type the name of the instance in the **Instance Name** field. This field only applies to redirected restores.
- j. Click **OK** to close the **Restore Command Line Options** dialog box.

14. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

15. Click **OK**.

## Restoring online backups that include archive logs

You can restore an online backup that includes archive logs to the original directory by specifying the **End of logs**, **Point In Time**, or **End of Backup** recovery types. The **End of Backup** recovery type is available only for database backups of DB2 9.5 and later.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.

6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a backup from the **Backups** table.

The backup contents appear below the **Contents of Backup** pane.

8. Expand the DB2 instance folder.

9. Select one or more database backups to restore.

10. Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

12. Select **Restore everything to its original location**.

13. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

14. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select **Restore and roll forward database**.
- c. Select a recovery types from the **Type of Recovery** list:

- **End of logs** recovers the database by performing a rollforward operation to the end of the logs.
  - **Point In Time** recovers the database by performing a rollforward operation to a specific point-in-time. Using the **Point In Time** recovery type requires you to type a date and time in the **Date and Time** field. Use the *yyyy-mm-dd hh:mm:ss* format. The time must be in the time zone of the client system.
  - **End of Backup** recovers the database by performing a rollforward operation to the end of the backup. The **End of Backup** option is valid for DB2 versions 9.5 and later.
- d. Select the number of sessions to use for the restore from the **Number of sessions** during restore list.

---


#### Note

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.
- g. Leave the **Database Partition Numbers** field blank. This field only applies to DPF environments.
- h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.
- The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.
- i. Leave the **Database Name** field blank. This field only applies to redirected restores.
- j. Leave the **Instance Name** field blank. This field only applies to redirected restores.

The following figure shows an example of the **Restore Command Line Options** dialog box.



k. Click **OK** to close the **Restore Command Line Options** dialog box.

15. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

Restore initiated.

16. Click **OK**.

## Restoring online backups that do not include archive logs

You can restore an online backup that does not include archive logs. Afterwards, you can use the `rollforward` command to roll the database forward to a desired point-in-time.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.



2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.

6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a backup from the **Backups** table.

The backup contents appear in the **Contents of Backup** pane.

8. Expand the DB2 instance folder.

9. Select one or more database backups to restore.

10. Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

12. Select **Restore everything to its original location**.

13. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

14. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select the **Restore only** option.
- c. Leave **Type of Recovery** blank.
- d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

#### Note


To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.

- g. Leave the **Database Partition Numbers** field blank. This field only applies to DPF environments.
- h. Leave the **Directory Path to Restore Archive Logs** field blank.
- i. Leave the **Database Name** field blank. This field only applies to redirected restores.
- j. Leave the **Instance Name** field blank. This field only applies to redirected restores.

The following figure shows an example **Restore Command Line Options** dialog box.



- k. Click **OK** to close the **Restore Command Line Options** dialog box.

15. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

Restore initiated.

16. Click **OK**.

17. After the restore completes, roll the database forward:

---

**Note**

If archived logs are enabled for backup, you can skip step a.

---

- a. Restore the archive logs from a file system backup to the `SQLLOGDIR` directory.

The `DB2 SQLLOGDIR` variable stores the location of the `SQLLOGDIR` directory.

---

**Note**

To skip the overhead process of searching for the available saved archived logs, you can use the Avamar file system plug-in instead of the Avamar Plug-in for DB2 to restore missing archived logs before you restore the database. Then specify the location of the log files when you perform a database rollforward operation.

---

- b. Use the `rollforward` command on the DB2 server to roll the database forward to the desired point-in-time.

The following commands perform a rollforward operation on the database to the end of the archive logs:

```
db2 rollforward db db_name to end of logs and complete
db2 rollforward db db_name to end of logs and complete overflow
log path (/tmp/alog)
```

where `db_name` is the database name.

---

**Note**

If a database is in a rollforward pending state and you do not run the `rollforward` command, the next Avamar Plug-in for DB2 backup of this database fails with an error message. The error message recommends that you roll the database forward. You can perform one more restore operation on a database that is in a rollforward pending state.

---

## Restoring only the archive logs

You can restore an online backup that includes only archive logs from an online backup.

**Procedure**

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.
6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.  
A list of backups that were performed on that date appears in the **Backups** table next to the calendar.
7. Select a backup from the **Backups** table.  
The backup contents appear below the **Backup History** pane.
8. Expand the DB2 instance folder.
9. Select one or more database backups to restore.
10. Select **Actions > Restore Now**.  
The **Restore Options** dialog box appears.
11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.  
The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.
12. Select **Restore everything to its original location**.
13. Click **More Options**.  
The **Restore Command Line Options** dialog box appears.
14. Set the plug-in options:
  - a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
  - b. Select **Restore only archive logs from an online backup**.
  - c. Leave **Type of Recovery** blank.
  - d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

#### Note

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
  - f. Type the password for the username in the **Instance Admin Password** field.
  - g. Leave the **Database Partition Numbers** field blank. This field only applies to DPF environments.
  - h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.
- 


#### Note

The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.

---

- i. Leave the **Database Name** field blank. This field only applies to redirected restores.
- j. Leave the **Instance Name** field blank. This field only applies to redirected restores.

The following figure shows an example **Restore Command Line Options** dialog box.



- k. Click **OK** to close the **Restore Command Line Options** dialog box.

15. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

Restore initiated.

16. Click **OK**.

## Recovering a database

Before you recover a database, you create an Avamar Plug-in for DB2 flag file and configure the `VENDOROPT` configuration parameter, and then recover the database by using Avamar Administrator.

You must recover one database at a time. Recovery of multiple databases in a single recovery operation is not supported.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.  
The **Backup, Restore and Manage** window appears.
2. Click the **Restore** tab.  
The top-left pane contains a list of domains.
3. Select the domain that contains the host of the DB2 server.  
You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.  
A list of Avamar clients appears in the pane below the domains list.
4. Select the host of the DB2 server.
5. Click the **By Date** tab.
6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.  
A list of backups that were performed on that date appears in the **Backups** table next to the calendar.
7. Select a backup from the **Backups** table.  
The backup contents appear in the **Contents of Backup** pane.
8. Expand the DB2 instance folder.
9. Select a database to restore.
10. Select **Actions > Restore Now**.  
The **Restore Options** dialog box appears.
11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.  
The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.
12. Select **Restore everything to its original location**.
13. Click **More Options**.  
The **Restore Command Line Options** dialog box appears.
14. Set the plug-in options:
  - a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
  - b. Select the **Recover** option.

- c. Select **End of Logs or Point in Time** from the **Type of Recovery** list.

---

**Note**

The **End of Logs** and **Point in Time** options are valid only for the **Recover** option.

---

- d. Leave the **Number of sessions during restore** list set to **1**.
- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.
- g. Leave the **Database Partition Numbers** field blank.

---

**Note**

The **Recover** option supports only a recovery of a single database at a time.

---

- h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.

The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.

- i. Leave the **Database Name** field and the **Instance Name** field blank.
  - j. Click **OK** to close the **Restore Command Line Options** dialog box.
15. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

16. Click **OK**.

## Restoring DB2 databases to a different client

You can restore DB2 databases, including automatic storage databases, to a client other than the original client by using Avamar Administrator. This type of restore is known as a redirected restore.

### Setting flags for automatic storage databases

To perform a redirected restore of an automatic storage database, you must set the `asm-restore-set-storagepaths` flag, the `restore-set-dbpath` flag, or both.

- The `asm-restore-set-storagepaths` flag set to true corresponds to the DB2's `ON path-list` parameter. A comma-separated list of directories that you select appears in the **Destination** column in the **Restore Options** dialog box. The `ON path-list` parameter redefines the storage paths associated with automatic storage databases.
- The `restore-set-dbpath` flag set to 1 corresponds to the new `DBPATH` as the first entry that you specify in a comma-separated list of directories in the **Destination** column in the **Restore Options** dialog box. The new storage path list does not use this `DBPATH`. The `restore-set-dbpath` flag is only relevant for automatic storage database restores.

## Rollforward after a redirected restore to a different host

The Avamar Plug-in for DB2 backup process does not save vendor configuration files during a database or log backup. A manual rollforward after a redirected restore requires these configuration files. Otherwise, the rollforward fails because it cannot find the log files.

1. Before you perform a manual rollforward after a redirected restore, ensure that all database vendor configuration files are available on the target system.  
Database configuration files include the file with the `logarchopt1` parameter setting. You can set up these configuration settings for the target database after the redirected restore completes.
2. Configure the `--logdest-id` and `--logdest-ap` parameters.  
A manual rollforward after a redirected restore to a different host requires these parameters. Add these parameters to the DB2 flag file. You can also configure the optional parameter, `--logdest-account`. [DB2 vendor parameters on page 104](#) provides more information about these parameters. [Creating the Avamar Plug-in for DB2 flag file on page 38](#) provides more information about parameters in the flag file.

---

### Note

The use of the `--logdest-id`, `--logdest-ap`, and `--logdest-account` parameters is specific to an archived log backup of the destination database. An archived log backup of the destination database can happen if a rollback occurs when a rollforward completes. These parameters replace the `--id`, `--account`, and `--ap` parameters that you set for the source client and use for archived log retrieval during a rollforward.

---

3. After the rollforward completes, you must remove the `--logdest-id`, `--logdest-ap`, and `--logdest-account` parameters from the DB2 flag file and replace the `--id`, `--account`, and `--ap` parameters. The values for the `--id`, `--account`, and `--ap` parameters correspond to the destination client.
4. After a restore or a change to database configuration settings, perform a full database backup to create a new baseline for the database backup and recovery history.

## Restoring the database to a different client

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.  
The **Backup, Restore and Manage** window appears.
2. Click the **Restore** tab.  
The top-left pane contains a list of domains.
3. Select the domain that contains the host of the DB2 server.  
You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.  
A list of Avamar clients appears in the pane below the domains list.
4. Select the host of the DB2 server.
5. Click the **By Date** tab.



6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.  
A list of backups that were performed on that date appears in the **Backups** table next to the calendar.
7. Select a backup from the **Backups** table.  
The backup contents appear below the **Backup History** pane.
8. Expand the DB2 instance folder.
9. Select one or more database backups to restore.
10. Select **Actions > Restore Now**.  
The **Restore Options** dialog box appears.
11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.  
The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.
12. Select **Restore everything to a different location**.
13. Click **Browse**.  
The **Browse for Restore Client** dialog box appears.
14. Select the target client from the client tree, and then click **OK**.  
The client name appears in the **Restore Destination Client** text box.
15. Click **Set Destination**.  
The **Set Destination** dialog box appears.
16. Type the destination for the restore in the **Save Target(s) in Directory** field. For an ASM restore, type a list of directories for storage paths. Separate entries in the list with a comma.
17. Click **OK**.  
The destination appears in the **Destination** column.
18. Click **More Options**.  
The **Restore Command Line Options** dialog box appears.
19. Set the plug-in options:
  - a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
  - b. Select the **Restore only** option.
  - c. Leave the **Recovery Type** panel blank. The **Recovery Type** options apply only to the **Recover** option.
  - d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

**Note**

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field and the instance owner's password in the **Instance Admin Password** field.
- f. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.  
The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.
- g. Type the name of the database in the **Database Name** field.
- h. Type the name of the instance in the **Instance Name** field.
- i. (Automatic storage databases only) Click **More** to display the **Enter Attribute** and **Enter Attribute Value** fields.
- j. In the **Enter Attribute** field, type `-- [avdb2] asm-restore-set-storagepaths.`

---


**Note**

You must precede the attribute with `-- [avdb2]`.

---

- k. In the **Enter Attribute Value** field, type `true`.
- l. Click **+**.
- m. In the **Enter Attribute** field, type `-- [avdb2] restore-set-dbpath.`
- n. In the **Enter Attribute Value** field, type `1`.
- o. Click **+**.
- p. Click **OK**.

The `asm-restore-set-storagepaths` and `restore-set-dbpath` flags appear in the box below the **+** and **-** buttons.



q. Click **OK** to close the **Restore Command Line Options** dialog box.

20. Click **OK** to close the **Restore Options** dialog box.

#### Note

You must precede the attribute with `-- [avdb2]`.

The following status message appears:

```
Restore initiated.
```

21. Click **OK**.

22. Roll the database forward. [Rolling the database forward on page 68](#) provides instructions.

## Rolling the database forward

You must roll the database forward if you used the **Restore only** option to restore an online backup. A rollforward operation does not apply to restores of offline backups.

### Procedure

- To manually roll the database forward to the desired point-in-time, use the `rollforward` command on the DB2 server. The following command is an example:

```
db2 rollforward db db_name to end of logs and complete
where db_name is the database name.
```

This example command rolls the database forward to the end of the archive logs.

---

### Note

If you do not run the `rollforward` command, subsequent Avamar Plug-in for DB2 backups and restores fail with an error message, which recommends that you roll the database forward.

---

## Restoring and recovering DPF

You can restore DB2 database partitions to the original location or to a different location by using Avamar Administrator.

Whether you restore the partition to the original location or to a different location depends on the location of the partition:

- If the partition is located on the catalog partition, restore the partition to the original location. [Restoring database partitions to the original location on page 69](#) provides instructions.
- If the partition is located on a non-catalog partition, perform a redirected restore. Restore the partition to a different location from the viewpoint of the catalog node. [Restoring database partitions to a different location on page 70](#) provides instructions.

Avamar Administrator lists all partition backups under the client that contains the catalog partition. You must restore database partitions from the catalog partition only. The Avamar Plug-in for DB2 restores each partition backup separately. You cannot restore all partition backups in a single restore operation.

Select the **Restore only** option in the **Restore Command Line Options** dialog box for all database partition restore operations. The **Restore and roll forward** option is not supported for database partition restore operations.

---

### Note

For an ASM redirected restore of a DPF database, pass the `ON path-list` option from the CLP to change the storage paths. Perform this operation from the catalog node only. Afterwards, the redirected restore continues to restore the non-catalog node without the need to pass the `ON path-list` option from the CLP. When you pass an `ON path-list` option during a redirected restore on an ASM non-catalog node, the restore fails.

---

## Restoring database partitions to the original location

Restore the partition to the original location when the partition is located on the catalog partition.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.  
The **Backup, Restore and Manage** window appears.
2. Click the **Restore** tab.  
The top-left pane contains a list of domains.
3. Select the domain that contains the host of the DB2 server.  
You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.  
A list of Avamar clients appears in the pane below the domains list.
4. Select the host of the DB2 server.
5. Click the **By Date** tab.
6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.  
A list of backups that were performed on that date appears in the **Backups** table next to the calendar.
7. Select a backup from the **Backups** table.  
The backup contents appear in the **Contents for Backup** pane.
8. Expand the DB2 instance folder.
9. Select a partition to restore.
10. Select **Actions > Restore Now**.  
The **Restore Options** dialog box appears.
11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.  
The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.
12. Select **Restore everything to its original location**.
13. Click **More Options**.  
The **Restore Command Line Options** dialog box appears.
14. Set the plug-in options:
  - a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
  - b. Select the **Restore only** option.

---

**Note**

The **Restore and roll forward database** option is not supported for database partition restore operations. [Restore options on page 102](#) provides more information about restore plug-in options.

---

- c. Leave the **Type of Recovery** list blank.
  - d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.
- 

**Note**

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
  - f. Type the password for the username in the **Instance Admin Password** field.
  - g. Leave the **Database Partition Numbers** field blank.
  - h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.  
The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.
  - i. Leave the **Database Name** field blank.
  - j. Leave the **Instance Name** field blank.
  - k. Click **OK** to close the **Restore Command Line Options** dialog box.
15. Click **OK** to close the **Restore Options** dialog box.
16. Click **OK**.

## Restoring database partitions to a different location

Restore the partition to a different location when the partition is located on a non-catalog partition. This type of restore is called a redirected restore.

**Procedure**

1. In Avamar Administrator, click the **Backup & Restore** launcher button.  
The **Backup, Restore and Manage** window appears.
2. Click the **Restore** tab.  
The top-left pane contains a list of domains.
3. Select the domain that contains the host of the DB2 server.  
You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.  
A list of Avamar clients appears in the pane below the domains list.
4. Select the host of the DB2 server.
5. Click the **By Date** tab.
6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a backup from the **Backups** table.

The backup contents appear in the **Contents of Backup** pane.

8. Expand the DB2 instance folder.

9. Select a partition to restore.

10. Select **Actions** › **Restore Now**.

The **Restore Options** dialog box appears.

11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

12. Select **Restore everything to a different location**.

13. Click **Browse**.

The **Browse for Restore Client** dialog box appears.

14. Select the target client from the client tree, and then click **OK**.

The client name appears in the **Restore Destination Client** text box.

15. Click **Set Destination**.

The **Set Destination** dialog box appears.

16. Type the destination for the restore in the **Save Target(s) in Directory** field. For an ASM restore, type a list of directories for storage paths. Separate entries in the list with a comma.

17. Click **OK**.

The destination appears in the **Destination** column.

18. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

19. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select the **Restore only** option.

---

#### Note

The **Restore and roll forward database** option is not supported for database partition restore operations. [Restore options on page 102](#) provides more information about restore plug-in options.

---

- c. Leave **Type of Recovery** blank.
- d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

**Note**

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
  - f. Type the password for the username in the **Instance Admin Password** field.
  - g. Leave the **Database Partition Numbers** field blank.
  - h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.  
The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.
  - i. Type the name of the database in the **Database Name** field.
  - j. Type the name of the DB2 instance in the **Instance Name** field.
  - k. Click **More** to display the **Enter Attribute** and **Enter Attribute Value** fields.
- 20.(ASM database restores only) Type the appropriate attributes and values to direct the Avamar Plug-in for DB2 to use storage redefinition options for ASM database restores:

- To use a value from the **Destination** field as the storage paths for the new database, set `asm-restore-set-storagepaths` to **true**:

```
-- [avdb2]asm-restore-set-storagepaths=true
```

---

**Note**

When you enable ASM mode for a restore, you can specify multiple values in the **Destination** field. Separate values for multiple storage paths with commas.

---

- To use a value from the **Destination** field as the new target database pathname for the new database, set `restore-set-dbpath` to **1**:

```
-- [avdb2]restore-set-dbpath=1
```

---

**Note**

The value 1 enables the `DBPATH ON` option. When the new `db_path` is the first pathname listed in the **Destination** field, the `db_path` is then not used in the new storage pathname list. You must set the `restore_set-storagepaths` flag, the `restore-set-dbpath` flag, or both flags to enable ASM mode for the restore.

---

- To use values from the **Destination** field as the storage paths and the `redirect_restore_target_path` values for the new target database pathname for the new database, set both of the following attributes:

```
-- [avdb2]asm-restore-set-storagepaths=true
```

```
-- [avdb2]restore-set-dbpath=1
```



---

**Note**

To comply with DB2 guidelines, call out the `ON path-list` from only the catalog node. For a catalog node, specify a list of locations for the storage paths in the **Destination** field. For a non-catalog nodes, specify only a single location in the **Destination** field with the effective `db_path` value that you used for restoring the catalog node.

---

After you set the options and attributes appear in the box below the **+** and **-** buttons.

21. Click **OK** to close the **Restore Command Line Options** dialog box.

22. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

23. Click **OK**.

**After you finish**

Perform a rollforward operation from the catalog node. [Rolling the database forward on page 68](#) provides more information.

## Recovering partitions

You can recover partitions, one at a time, by using Avamar Administrator. Before you perform a recovery operation from Avamar Administrator, create an Avamar Plug-in for DB2 flag file. The recovery operation requires you to configure the `VENDOROPT` configuration parameter. The IBM DB2 documentation provides more information about the `VENDOROPT` parameter.

---

**Note**

You must recover one partition at a time. Recovery of multiple partitions in a single recovery operation is not supported.

---

**Procedure**

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.

6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a backup from the **Backups** table.

The backup contents appear in the **Contents of Backup** pane.

8. Expand the DB2 instance folder.
9. Select a partition to restore.
10. Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

12. Select **Restore everything to its original location**.

13. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

14. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select the **Recover** option.
- c. Select **End of Logs** or **Point in Time** from the **Type of Recovery** list.

---

#### Note

The **End of Logs** and **Point in Time** options are valid only for the **Recover** option.

---

- d. Leave the **Number of sessions during restore** list set to 1.
- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.
- g. Specify a single partition number in the **Database Partition Numbers** field.

---

#### Note

The **Recover** option supports only a recovery of a single partition at a time.

---

- h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.

The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.

- i. Leave the **Database Name** field and the **Instance Name** field blank.
- j. Click **OK** to close the **Restore Command Line Options** dialog box.

15. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

16. Click **OK**.

## Restoring table spaces in a stand-alone DB2 environment

You can use Avamar Administrator to restore one or more table spaces from a backup.

To restore the SYSCATSPACE table space from DB2 version 10.1 or later databases, you must specify the `tbs-offline-restore-mode=true` option in the **Enter Attribute** and **Enter Attribute Value** fields. The following procedure includes instructions.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.

6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a full backup from the **Backups** table.

The backup contents appear in the **Contents of Backup** pane.

The **Browse for Image Restore** and **Browse for Granular Restore** buttons appear above the directory tree in the **Contents of Backup** pane.

8. Select the top-level folder to select the entire plug-in, or select one or more databases for the granular browse operation.

---


### Note

You cannot use the Granular level browse feature for database backups that you create by using the DB2 CLP.

---

9. Click the **Browse for Granular Restore** button (.

The **Select Destination Client** dialog box appears.



10. Leave **Restore everything to its original location** selected and click **OK**.

---

**Note**

You cannot perform a redirected restore of a DB2 table space to a DB2 stand-alone environment.

---

The **Contents of Backup** pane lists a directory tree for the selection that you made.

11. Expand the folders in the directory tree to view table spaces available for restore.  
 12. Select one or more table spaces.

---

**Note**

The **Backup, Restore and Manage** window does not display the table space size correctly in the **Size** column. EMC plans to fix this issue in a future release.

---

13. Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

14. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

15. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

16. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select **Restore only** to restore table spaces other than the SYSCATSPACE table space.
- c. To restore the SYSCATSPACE table space, select **Restore and roll forward database**, and then select **End of logs** from the **Type of Recovery** list.
- d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---


**Note**

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
  - f. Type the password for the username in the **Instance Admin Password** field.
  - g. Leave the **Database Partition Numbers** field blank.
  - h. Leave the **Directory Path to Restore Archive Logs** field blank.
  - i. Leave the **Database Name** field blank.
  - j. Type the name of the DB2 instance in the **Instance Name** field.
- 17.(Renamed table spaces only) Complete the following steps to restore renamed table spaces:
- a. Click **More** to display the **Enter Attribute** and **Enter Attribute Value** fields.
  - b. Type `--[avdb2] renamed_tablespace_list` in the **Enter Attribute** field.
  - c. Type the name of the renamed table space in the **Enter Attribute Value** field.
  - d. Click **+**.

The attribute and value appear in the box below the **+** and **-** buttons.



- e. Click **OK** to close the **Restore Command Line Options** dialog box.
  - 18.(SYSCATSPACE table space from DB2 version 10.1 or later) Complete the following steps to restore the SYSCATSPACE table space from DB2 version 10.1 or later databases:
    - a. Click **More** to display the **Enter Attribute** and **Enter Attribute Value** fields.
    - b. Type `-- [avdb2] tbs-offline-restore-mode` in the **Enter Attribute** field.
    - c. Type `true` in the **Enter Attribute Value** field.
    - d. Click **+**.
    - e. Click **OK** to close the **Restore Command Line Options** dialog box.
  - 19.Click **OK** to close the **Restore Options** dialog box.
- The following status message appears:
- Restore initiated.
- 20.Click **OK**.

## Restoring table spaces in a DB2 DPF environment

You can use Avamar Administrator to restore a table space that is not local to the catalog partition by performing a redirected restore from the catalog node to the target node.

To restore the SYSCATSPACE table space from DB2 version 10.1 or later databases, you must specify the `tbs-offline-restore-mode=true` option in the **Enter Attribute** and **Enter Attribute Value** fields. The following procedure includes instructions.

---

### Note

You cannot specify a recovery type for a table space restore in a DPF environment.

---

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.

The **Backup, Restore and Manage** window appears.

2. Click the **Restore** tab.

The top-left pane contains a list of domains.

3. Select the domain that contains the host of the DB2 server.

You cannot view clients outside the domain for the login account. To view all clients, log in to the root domain.

A list of Avamar clients appears in the pane below the domains list.

4. Select the host of the DB2 server.

5. Click the **By Date** tab.

6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.

A list of backups that were performed on that date appears in the **Backups** table next to the calendar.

7. Select a full backup from the **Backups** table.


The backup contents appear in the **Contents of Backup** pane.

The **Browse for Image Restore** and **Browse for Granular Restore** buttons appear above the directory tree in the **Contents of Backup** pane.

8. Select the top-level folder to select the entire plug-in, or select one or more databases for the granular browse operation.

9. Click the **Browse for Granular Restore** button ()

The **Select Destination Client** dialog box appears.



10. Set the options:

- a. Click **Restore everything to a different location**.
- b. Click **Browse**.

The **Browse for Restore Client** dialog box appears.

- c. Click the domain that contains the target DPF node.
- d. Select the DPF node that contains the target partition for the table space restore.
- e. Click **OK** to close the **Browse for Restore Client** dialog box.
- f. Click **OK** again to close the **Set Destination Client** dialog box.

11. Expand the folders in the directory tree to view table spaces available for restore.

12. Select one or more table spaces.

---

#### Note

The **Backup, Restore and Manage** window does not display the table space size correctly in the **Size** column. EMC plans to fix this issue in a future release.

---

13. Select **Actions > Restore Now**.

The **Restore Options** dialog box appears.

14. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.

The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.

15. Select **Restore everything to a different location**.

16. Click **Browse**.

The **Browse for Restore Client** dialog box appears.

17. Select the same DPF node that you previously selected.

18. In the **Destination** field, type the pathname to the database.

19. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

20. Set the plug-in options:



- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select **Restore only** to restore table spaces other than the SYSCATSPACE table space.
- c. To restore the SYSCATSPACE table space, select **Restore and roll forward database**, and then select **End of logs** from the **Type of Recovery** list.
- d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

#### Note

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.
- g. Leave the **Database Partition Numbers** field blank.
- h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.

---

#### Note

If the backup for this restore operation is an online backup and you intend to restore archive log files, you must complete the **Directory Path to Restore Archive Logs** field.

---

The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.

- i. Type the name of the database from which the backup was originally taken in the **Database Name** field.
- j. Type the name of the DB2 instance in the **Instance Name** field.
- k. (SYSCATSPACE table space from DB2 version 10.1 or later) Complete the following steps to restore the SYSCATSPACE table space from DB2 version 10.1 or later databases:
  - a. Click **More** to display the **Enter Attribute** and **Enter Attribute Values** fields.
  - b. Type `--[avdb2] tbs-offline-restore-mode` in the **Enter Attribute** field.
  - c. Type `true` in the **Enter Attribute Value** field.
  - d. Click **+**.
- l. Click **OK** to close the **Restore Command Line Options** dialog box.

21. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

22. Click **OK**.

23. Manually roll the table space forward to the desired point-in-time by using the DB2 `rollforward` command on the DB2 server.

## Recovering retired clients

The Avamar system maintains backups for retired clients for the length of time determined by the retention policy. You can restore a backup from a retired client by using Avamar Administrator.

### Procedure

1. In Avamar Administrator, click the **Backup & Restore** launcher button.  
The **Backup, Restore and Manage** window appears.
2. Click the **Restore** tab.  
The top-left pane contains a list of domains.
3. Click the `MC_RETIRE`D domain.
4. Select the client from the `MC_RETIRE`D domain.
5. Click the **By Date** tab.
6. Select the backup date from the calendar. Valid backups occurred on dates with a yellow highlight.  
A list of backups that were performed on that date appears in the **Backups** table next to the calendar.
7. Select a backup from the **Backups** table.  
The backup contents appear as a list in the **Contents of Backup** pane.
8. Expand the folders to display the DB2 instance folder.
9. Select the database backup to restore.
10. Select **Actions > Restore Now**.  
The **Restore Options** dialog box appears.
11. From the **Avamar encryption method** list, select an encryption method to use for client/server data transfer during this restore.  
The encryption technology and bit strength for a client/server connection depend on several factors, including the client platform and Avamar server version. The *EMC Avamar Product Security Guide* provides more information.
12. Select **Restore everything to a different location**.
13. Click **Browse**.  
The **Browse for Restore Client** dialog box appears.
14. Select the target client from the **Browse for Client Destination** dialog box.

---

### Note

The target client name has the same name as the `MC_RETIRE`D client name.

---

The target client name appears in the **Restore Destination Client** field.

15. Click **Set Destination**.

The **Set Destination** dialog box appears.

16. Click **Browse**.

The **Browse for File, Folder, or Directory** dialog box appears.

## 17. Click the DB2 plug-in.

The **Browse Command Line Options** dialog box appears.

## 18. Type the DB2 instance credentials:

- a. In the **DB2 Instance Name** field, type the name of the DB2 instance to browse.
- b. In the **Instance Admin Username**, type the instance owner or system admin username.
- c. In the **Instance Admin Password**, type the password for the username.

19. Click **OK** to close the **Set Destination** dialog box.

The database instance appears in the **Destination** column of the **Items Marked for Restore** table.

20. Click **More Options**.

The **Restore Command Line Options** dialog box appears.

## 21. Set the plug-in options:

- a. From the **Encryption method from Data Domain system** list, select the encryption method to use for data transfer between the Data Domain system and the client during the restore.
- b. Select the **Restore and roll forward database** option.

---

**Note**

Alternately, you can select the **Restore only** option and perform a manual rollforward operation after the restore completes. To perform a manual rollforward operation, use the `overflow log path` option with the `rollforward` command, and then recover the database to the end of logs or to a point-in-time. DB2 documentation provides more information about the `rollforward` command.

---

- c. Select one of the following recovery types from the **Type of Recovery** list:
  - **End of logs** recovers the database by performing a rollforward operation to the end of logs.
  - **Point In Time** recovers the database by performing a rollforward operation to a specific point-in-time. To use the **Point In Time** recovery type requires you to type a date and time in the **Date and Time** field. Use the `yyyy-mm-dd hh:mm:ss` format. The time must be in the time zone of the client system.
  - **End of Backup** recovers the database by performing a rollforward operation to the end of the backup. The **End of Backup** option is valid for DB2 versions 9.5 and later.
- d. Select the number of sessions to use for the restore from the **Number of sessions during restore** list.

---

**Note**

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

- e. Type the instance owner or system admin username in the **Instance Admin Username** field.
- f. Type the password for the username in the **Instance Admin Password** field.
- g. Leave the **Database Partition Numbers** field blank.
- h. Type the fully qualified pathname of an existing top-level directory in the **Directory Path to Restore Archive Logs** field.  
The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.
- i. Type the name of the database from which the backup was originally taken in the **Database Name** field.
- j. Type the name of the DB2 instance in the **Instance Name** field.
- k. Click **OK** to close the **Restore Command Line Options** dialog box.

22. Click **OK** to close the **Restore Options** dialog box.

The following status message appears:

```
Restore initiated.
```

23. Click **OK**.

## Disaster recovery

With an effective data backup plan in place, you can successfully recover a DB2 server after the loss of the DB2 application or server hardware.

---

### Note

To perform a manual rollforward after you restore the DB2 server and DB2 applications, follow the guidelines in [Rollforward after a redirected restore to a different host on page 64](#).

---

## Recovering the DB2 application

As long as Avamar components on a DB2 server are intact, you can recover only the DB2 application.

### Procedure

1. Uninstall the current installation of the DB2 application.
2. Delete all DB2 application files and directories.
3. Install the same version of the DB2 application that was previously installed.
4. Re-create the DB2 instance (UNIX) or DB2 copy (Windows) with the same name that was previously used.
5. Restore a full backup of the DB2 database to the original location by completing the appropriate instructions in [Restoring DB2 databases to the original location on page 51](#).

## Recovering the DB2 server

To recover the DB2 server requires a replacement computer.

**Procedure**

1. Install the same version and release of the operating system on the replacement computer.
2. Log in to the computer.
3. Configure the computer with the IP address and hostname from the old computer.
4. Install the same version of the DB2 application.
5. Re-create the DB2 instance (UNIX) or DB2 copy (Windows) with the same name that was previously used.

Refer to the vendor documentation for instructions.

6. Install and register the Avamar file system client. [Installing the Avamar file system client on page 25](#) provides instructions.
7. Install the Avamar Plug-in for DB2. [Installation on page 23](#) provides instructions.

## Recovering the DB2 server in a DPF environment

**Procedure**

1. Install the DB2 application on the catalog node and other participating nodes.
2. Re-create the DB2 instance (UNIX) or DB2 copy (Windows) with the same name that was previously used.
3. Restore the catalog node backup by performing a restore from the catalog node. [Restoring and recovering DPF on page 68](#) provides more information.
4. Restore all other node backups by performing a redirected restore. [Restoring and recovering DPF on page 68](#) provides more information.



# CHAPTER 5

## Backup and Restore with DB2 CLP

This chapter includes the following topics:

- [Using DB2 CLP for backups and restores](#)..... 88
- [Backing up databases from the DB2 CLP](#)..... 90
- [Restoring databases and table spaces from the DB2 CLP](#).....93
- [Performing redirected restores from the DB2 CLP](#).....93
- [Restoring backup images from Avamar versions before 7.0](#)..... 95
- [Recovering DB2 with the DB2 CLP](#).....96
- [DB2 CLP limitations](#).....96
- [Setting the expiration and retention for backups](#)..... 97

## Using DB2 CLP for backups and restores


The DB2 CLP works with the Avamar Plug-in for DB2 to provide on-demand backups, restores, and database recoveries. You can perform these operations from the command line on the client system that hosts the DB2 server.

The Avamar Plug-in for DB2 supports the following DB2 CLP commands:

- `db2 backup`
- `db2 restore`
- `db2 recover`
- `db2 rollforward`
- `db2 archive`

The following figure shows the process flow between the Avamar software and the DB2 software.

**Figure 3** Avamar software and DB2 CLP process flow



The following steps describe the process flow that occurs when you use the DB2 CLP to perform on-demand backup or restore operations.

1. DB2 starts one or more fenced vendor processes on UNIX or one or more threads on Windows. The number of fenced vendor processes or threads depends on the number of sessions requested during the backup or restore operation.
2. Each of the processes or threads invokes the vendor APIs.
3. The vendor APIs start the `avdb2` process, which in turn starts `avtar` processes and other miscellaneous operations.

---

### Note

The `avdb2` process requires exclusive access to some of the system resources. After a backup or restore operation, the `avdb2` process requires approximately 1 to 2 minutes to release the system resources. Allow sufficient time before you start another CLP operation.

4. The vendor APIs start an `avtar` process for each stream that you specify in the Avamar Plug-in for DB2 flag file.



- a. The DB2 data blocks pass from the vendor APIs to `avtar` during a backup operation.
- b. Vendor APIs read data from `avtar` during a restore operation.

---

#### Note

To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.

---

All backup images that you create by specifying multiple sessions use a sequence number as an extension. The sequence number identifies the backup piece.

After a successful backup, the Avamar Plug-in for DB2 represents all backup pieces from all backup sessions as one backup image or label.

You can restore backups that you create with multiple session in a single restore session. The Avamar Plug-in for DB2 restores the entire backup image even when you select only one backup piece.

5. The `avtar` process stores the data to either the Avamar server or a Data Domain system depending on what back-end device you specify.
6. The vendor library communicates a success or failure status to the DB2 server.

## Backup label and image names

Backup label names and image names identify the type of backup and whether the backup was created from Avamar Plug-in for DB2 or from the command line.

Backup label and image names use the same naming convention whether you create a backup from Avamar Plug-in for DB2 or from the DB2 CLP. Backup label names include the prefix “CLI” when you create a backup by using the `db2 backup` command. [Backup naming conventions on page 50](#) provides more information.

## Avamar Plug-in for DB2 flag file configuration

Before you use the DB2 CLP, create an Avamar Plug-in for DB2 flag file. The DB2 CLP requires you to configure the configuration parameter for a DB2 recovery operation and configure `LOGARCHOPT1` for a DB2 rollforward operation.

[Specifying DB2 vendor parameters on page 89](#) provides information about parameters you can use with `db2` commands.

## Specifying DB2 vendor parameters

Include only parameters in the Avamar Plug-in for DB2 flag file that are relevant to the backup or restore operation.

Remove all parameters from the flag file that are not relevant to the backup or restore operation. The DB2 CLP does not recognize comment symbols, such as the hash symbol (`#`), when you include them in a flag file. For example, the DB2 CLP uses the following parameter despite the `#` symbol:

```
#--logfile=/abc
```

[DB2 vendor parameters on page 104](#) provides more information about parameters that you can specify in the flag file for DB2 CLP backups and restores.

## Backing up databases from the DB2 CLP

The DB2 CLP enables you to perform on-demand backups to either the Avamar server or a Data Domain system. Use the DB2 CLP to back up an entire database in offline or online mode, or to back up a single table space from an online database. The IBM website provides more information about the DB2 CLP.

### Procedure

1. Log in to the Avamar Plug-in for DB2 client with DB2 instance owner's credentials.
2. Create an Avamar Plug-in for DB2 flag file that includes all necessary parameters for the backup. [Creating the Avamar Plug-in for DB2 flag file on page 38](#) provides more information.
3. To use a Data Domain system for the backup, add the following parameters to the flag file:

```
--ddr=true
--ddr-index=index_number
```

where *index\_number* is the identification number of the Data Domain system to use for the backup. Contact the Avamar administrator to determine the index number of the Data Domain system.

4. To back up data from a DPF node, add the following parameters to the flag file:

```
--dbpartitionnums=partition_numbers
--catnode=catnode_number
```

where:

- *partition\_numbers* is a list of partitions for a single-system view backup. Separate each partition number by a comma.
  - *catnode\_number* specifies the partition number of the catalog node.
5. Type the `db2 backup` command with appropriate parameters. The following topics include example backup commands:
    - [Example command to back up a database in offline mode on page 90](#)
    - [Example command to back up a database in online mode on page 91](#)
    - [Example command to back up a table space in online mode on page 92](#)

## Example command to back up a database in offline mode

You can use the `db2 backup db` command to back up a database in offline mode.

The following table provides an example command to back up an entire database in offline mode.

**Table 2** Command to back up a database in offline mode

| Operating system | Command                                                                                                                                                                                                                                                                                                                                                                                                         |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Windows          | <pre>db2 backup db sample load Avamar_client_installation_dir \bin\libavdb2.dll options @pathname\avdb2.flg</pre> <p>where:</p> <ul style="list-style-type: none"> <li>• <i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> <li>• <i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul>          |
| UNIX             | <pre>db2 backup db sample load Avamar_client_installation_dir/lib/libdb2_avamarloader.so options @pathname/avdb2.flg</pre> <p>where:</p> <ul style="list-style-type: none"> <li>• <i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> <li>• <i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul> |

## Example command to back up a database in online mode

You can use the `db2 backup db` command to back up a database in online mode.

The following table provides an example command to back up an entire database in online mode.

**Table 3** Command to back up a database in online mode

| Operating system | Command                                                                                                                                                                                                                                                                                                                                                                                                                 |
|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Windows          | <pre>db2 backup db sample load Avamar_client_installation_dir \bin\libavdb2.dll open 5 sessions options @pathname \avdb2.flg</pre> <p>where:</p> <ul style="list-style-type: none"> <li>• <i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> <li>• <i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul> |
| UNIX             | <pre>db2 backup db sample load Avamar_client_installation_dir/lib/libdb2_avamarloader.so open 5 sessions options @pathname/avdb2.flg</pre> <p>where:</p> <ul style="list-style-type: none"> <li>• <i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> </ul>                                                                                                |

**Table 3** Command to back up a database in online mode (continued)

| Operating system | Command                                                                                                                                       |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|
|                  | <ul style="list-style-type: none"> <li><i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul> |

**Note**

The Avamar Plug-in for DB2 supports a maximum of 10 sessions.

## Example command to back up a table space in online mode

You can use the `db2 backup db` command to back up a single table space in online mode.

The following table provides an example command to back up a single table space in online mode from the sample database. The example command also shows how to use the `dedup_device` option.

**Table 4** Command to back up a table space in online mode

| Operating system | Command                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Windows          | <pre>db2 backup db sample tablespace(TBSPACE1) online load Avamar_client_installation_dir\bin\libavdb2.dll open 5 sessions options @pathname\avdb2.flg dedup_device</pre> <p>where:</p> <ul style="list-style-type: none"> <li><i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> <li><i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul>           |
| UNIX             | <pre>db2 backup db sample tablespace(TBSPACE1) online load Avamar_client_installation_dir/lib/libdb2_avamarloader.so open 5 sessions options @pathname/avdb2.flg dedup_device</pre> <p>where:</p> <ul style="list-style-type: none"> <li><i>Avamar_client_installation_dir</i> is the installation directory pathname of the Avamar client software.</li> <li><i>pathname</i> is the complete directory pathname of the Avamar Plug-in for DB2 flag file.</li> </ul> |

## Restoring databases and table spaces from the DB2 CLP

You can perform various restore operations from the DB2 CLP. For example, you can restore the most recent backup or you can specify a timestamp to restore a specific backup. You can restore the entire database or restore individual table spaces.

To restore DB2 databases in a DPF environment, use the DB2 documentation. This guide does not provide instructions for performing restores in a DPF environment from the DB2 CLP.

### Specifying multiple sessions for a restore from the DB2 CLP

Add the `--timeout-new-connection` option to the Avamar Plug-in for DB2 flag file when you specify multiple sessions for a restore.

#### Procedure

- Before you specify multiple sessions for a restore you perform from the DB2 CLP, add `--timeout-new-connection=40` to the Avamar Plug-in for DB2 flag file.

[Creating the Avamar Plug-in for DB2 flag file on page 38](#) provides more information.

---

#### Note

A restore that specifies multiple session might fail if you do not include `--timeout-new-connection=40` in the Avamar Plug-in for DB2 flag file.

---

## Performing redirected restores from the DB2 CLP

You can perform redirected restores from the DB2 CLP. A redirected restores enables you to restore a backup to a target other than the original one. You can restore backups to a different system, instance, or database.

To restore one instance to another instance, include the `--db2-source-instance` parameter in the Avamar Plug-in for DB2 flag file. The value of the `--db2-source-instance` parameter is the name of the source instance.

### Example procedure to restore an instance to a different instance

You can redirect a restore of an instance to a different instance by using DB2 commands.

#### Procedure

- Create the flag file and include the following parameters:

```
--id=user-1@/clients/hostA.avamar.emc
--password=obfuscated password
--sysdir=/usr/local/avamar/etc
--db2-source-instance=db2inst1
--redirected_restore_target=db2inst2
```

[Creating the Avamar Plug-in for DB2 flag file on page 38](#) provides more information.

- Attach to the target instance by typing the following command:

```
db2 attach to db2inst2
```

3. Set the `DB2INSTANCE` environment variable to the target instance, `db2inst2`.
4. Type the appropriate restore command for the system type:
  - For Windows, type the following command:
 

```
db2 restore db sample load Avamar_client_installation_dir\bin
\libavdb2.dll options @pathname\avdb2.flg redirect
```

 where:
    - *Avamar\_client\_installation\_dir* is the installation directory pathname of the Avamar client software.
    - *pathname* is the complete directory pathname of the Avamar Plug-in for DB2 flag file.
  - For UNIX, type the following command:
 

```
db2 restore db sample load Avamar_client_installation_dir/lib/
libdb2_avamarloader.so options @pathname/avdb2.flg redirect
```

 where:
    - *Avamar\_client\_installation\_dir* is the installation directory pathname of the Avamar client software.
    - *pathname* is the complete directory pathname of the Avamar Plug-in for DB2 flag file.
5. Run the `set table space containers` command for each table space whose containers you want to redefine. The DB2 documentation provides more information.
6. After you successfully complete all previous steps, type the following `db2 restore db` command with the `continue` option:
 

```
db2 restore db sample continue
```

## Example restore that uses an automatically generated script

You can redirect a restore of an instance to a different instances by using an automatically generated script. The DB2 documentation provides complete details about performing redirected restore to a different DB2 instance.

### Procedure

1. Log in as the target instance, `db2inst1`, and then generate a redirected restore script:
  - For Windows, type the following command:
 

```
db2 restore db sample load Avamar_client_installation_dir\bin
\libavdb2.dll options @pathname\avdb2.flg generate script
script_path\my_redirect.clp
```

 where:
    - *Avamar\_client\_installation\_dir* is the installation directory pathname of the Avamar client software.
    - *pathname* is the complete directory pathname of the Avamar Plug-in for DB2 flag file.
    - *script\_path* is the complete pathname where the script is saved.
  - For UNIX, type the following command:
 

```
db2 restore db sample load Avamar_client_installation_dir/lib/
libdb2_avamarloader.so options @pathname/avdb2.flg generate
script script_path/my_redirect.clp
```

where:

- *Avamar\_client\_installation\_dir* is the installation directory pathname of the Avamar client software.
- *pathname* is the complete directory pathname of the Avamar Plug-in for DB2 flag file.
- *script\_path* is the complete pathname where the script is saved.

2. Open the script in an editor and define the following parameters:

- ON

---

#### Note

For Windows operating systems, you must specify a drive letter as the first entry if the database does not exist and you do not specify the `DBPATH ON` parameter. If you specify a pathname, the script returns an error.

---

- DBPATH
- NEWLOGPATH
- INTO
- TAKEN AT
- REPLACE EXISTING REDIRECT
- WITHOUT ROLLING FORWARD

For example:

```
ON '/home/db2inst2'
INTO sample1
```

where `/home/db2inst2` is the home directory of the new instance.

---

#### Note

If the backup created table spaces, set the `set tablespace containers` parameter to the appropriate value, if necessary.

---

3. Change the directory to the *script\_path* directory, and then type the following command:

```
db2 -tvf my_redirect.clp
```

## Restoring backup images from Avamar versions before 7.0

Backups from the Avamar Plug-in for DB2 before release 7.0 do not include a timestamp in the backup image name. The naming convention for backup image names changes in release 7.0 to include a timestamp.

[Backup naming conventions on page 50](#) provides more information.

To restore a backup from a release of the Avamar Plug-in for DB2 previous to 7.0, provide the label number of the backup. Specify the label number by including the `--labelnum` parameter in the Avamar Plug-in for DB2 flag file.

The following flag file includes the `--labelnum` parameter, which enables you to restore DB2 from a previous version of the Avamar Plug-in for DB2:

```
--id=user-1@/clients/hostA.avamar.emc
--password=obfuscated password
--sysdir=/usr/local/avamar/etc
--labelnum=136
```

## Recovering DB2 with the DB2 CLP

You can use the `db2 recover db` command to recover a database in a stand-alone DB2 installation.

The database name in the following commands is sample.

To run the `db2 recover db` command by using the plug-in vendor library, set the `VENDOROPT` parameter to the flag file:

```
update db cfg for database_name using VENDOROPT @/pathname/avdb2.flg
```

where *database\_name* is the name of the database and *pathname* is the directory that contains the Avamar Plug-in for DB2 flag file.

### Procedure

- To recover the database, type the following command:

```
db2 recover db sample
```

- To recover partition 1 of the database, type the following command:

```
db2 recover db sample on dbpartitionnum(1)
```

[DB2 CLP limitations on page 96](#) provides more information.

---

### Note

In a DPF environment, the Avamar Plug-in for DB2 supports only single-partition recoveries.

---

- To roll the database forward to the end of backup, and then run a `complete` operation, type the following command:

```
db2 rollforward db sample to end of backup and complete
```

- To roll the database forward to the end of logs, and then run a `complete` operation, type the following command:

```
db2 rollforward db sample to end of logs and complete
```

- To roll the database forward on all nodes in a DPF environment, type the following command:

```
db2 rollforward db sample to end of logs on all dbpartitionnums
```

- To roll the database forward on partitions 1 and 3 to the end of backup, type the following command:

```
db2 rollforward db sample to end of backup on dbpartitionnums(1,3)
```

## DB2 CLP limitations

The Avamar Plug-in for DB2 limits the use of some operations from the DB2 CLP:

- You cannot restore incremental or delta backups that you create from the DB2 CLP by using Avamar Administrator.



**Note**

DB2 CLP incremental and delta backup images are not linked. If the base backup expires, Avamar removes it, which results in data loss. Subsequently, there is no snapview available for all the required pieces. Adjust the expiry so that all required full, incremental, and delta pieces are available for restore.

- The Avamar Plug-in for DB2 supports one restore operation of a partition at a time. This limitation applies to restores by using the `db2 restore` and `db2 recover` commands.
- The Avamar Plug-in for DB2 does not support the `db2 recover db` command for dropped databases.

**Note**

To recover a dropped database, use the `db2 restore` command followed by the `db2 rollforward` command. [Recovery of a dropped database fails with error code 30 on page 112](#) provides more information.

- You cannot use the Point-in-Time (PIT) recovery type in a DPF environment.
- You cannot recover multiple partitions from the DB2 CLP. A recovery operation can only be performed on one partition at a time.
- Archived logs must have an appropriate expiry date that corresponds to the backup image. Archived logs are not linked to a backup. Avamar purges backup logs that expire if you restore the most recent backup in which the archive logs have been deleted due to the expiry date.

## Setting the expiration and retention for backups

You can specify the `--expires` and `--retention` parameters to set an expiration time for a backup.

You can specify a timestamp value or a calendar day, month, or year for the `--expires` parameter. The *EMC Avamar Administration Guide* provide more information about the `--expires` and `--retention` parameters.

You can manually adjust the expiration time and retention policy after a backup completes by using the `mccli backup edit` command. The *EMC Avamar Management Console Command Line Interface (MCCLI) Programmer Guide* provides more information.

To ensure that all backup pieces are available for an incremental restore and rollforward operation, set the `--expires` parameter to the same timestamp for all related backups.

**Procedure**

- If you need to change an expiration date, manually adjust the expiration date for all related backups.
- If you specify a count for the `--expires` parameter, ensure that all expiration dates for all backup pieces are synchronized.



# APPENDIX A

## Plug-in Options

This appendix includes the following topics:

- [Plug-in options](#)..... 100
- [Performance options](#)..... 100
- [Backup options](#)..... 101
- [Restore options](#)..... 102
- [Table space restore option](#)..... 104
- [DB2 vendor parameters](#)..... 104

## Plug-in options

Plug-in options allow you to control specific actions for on-demand backups, restores, and scheduled backups. The plug-in options that are available depend on the operation type and client plug-in type.

You can specify plug-in options in Avamar Administrator for on-demand backup or restore operations, or when you create a dataset for a scheduled backup. Plug-in options are set using the graphical user interface (GUI) controls (text boxes, checkboxes, radio buttons, and so forth). In addition to using the GUI controls, you can type an option and its value in the **Enter Attribute** and **Enter Attribute Value** fields for special circumstances.

[Specifying backup and restore options as normal text on page 116](#) provides more information.

---

### Note

The Avamar software does not check or validate the information that you type in the **Enter Attribute** and **Enter Attribute Value** fields. In addition, the values in the **Enter Attribute** and **Enter Attribute Value** fields override settings that you specify with the GUI controls.

Detailed instructions on how to access and set plug-in options during a backup or restore are available in [Chapter 3, Backup on page 37](#) and [Chapter 4, Restore and Recovery on page 49](#).

## Performance options

DB2 includes options that affect backup and restore performance. You can specify these options with CLP operations or from Avamar Administrator.

The following table lists DB2 performance options.

**Table 5** Performance options

| Option name | Description                                                                                                         |
|-------------|---------------------------------------------------------------------------------------------------------------------|
| buffer size | DB2 backup/restore buffer size in page units.                                                                       |
| num-buffers | The number of backup/restore buffers used by DB2.                                                                   |
| parallelism | The number of table spaces read in parallel in a backup or the number of DB2 buffer manipulators used in a restore. |

---

### Note

To set performance options with Avamar Administrator, use the instructions in [Specifying backup and restore options as normal text on page 116](#). Precede the option name with the prefix, [avdb2].

The DB2 database system automatically uses optimal values for these options. Some system configurations, however, might require custom tuning, especially when you use the `dedup_device` option with a CLP operation or the **Optimize backup deduplication** option with Avamar Administrator. The DB2 documentation provides guidelines for the range of values that you can use for these options.

## Backup options

Backup options enable you to control backup functionality that is specific to the Avamar Plug-in for DB2. You can specify plug-in options for on-demand and scheduled backups.

The following table lists options that are available for the Avamar Plug-in for DB2 when you perform an on-demand backup or when you configure a dataset for scheduled backups.

**Table 6** Backup plug-in options

| Option                                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|---------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Create an online backup               | <p>Backs up the database while it is operational. This type of backup is a hot backup.</p> <hr/> <p><b>Note</b></p> <p>You must enable DB2 Archive Logging to successfully perform online backups.</p>                                                                                                                                                                                                                                                                  |
| Exclude archive logs in online backup | Excludes the archive logs from the backup. If you exclude the archive logs from a database backup, ensure that you include the archive logs in file system backups. Failure to do so can result in loss of data.                                                                                                                                                                                                                                                        |
| Optimize backup deduplication         | <p>Enables the DB2 <code>dedup_device</code> option for the backup.</p> <hr/> <p><b>Note</b></p> <p>Only specific DB2 versions support the <code>dedup_device</code> option. Check the vendor documentation to determine if the DB2 version supports the <code>dedup_device</code> option. A backup fails if you select the <b>Optimized backup deduplication</b> option for a backup of a DB2 database that does not support the <code>dedup_device</code> option.</p> |
| Instance Admin Username               | Specifies the instance owner or system admin username.                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Instance Admin Password               | Specifies the password for the username.                                                                                                                                                                                                                                                                                                                                                                                                                                |
| Database Partition Numbers            | <p>Specifies database partition numbers to use for the backup:</p> <ul style="list-style-type: none"> <li>To specify all database partitions, type <b>ALL</b> or <b>all</b>.</li> <li>To specify a list of partitions, for example, partitions 1, 2, and 3, type <b>1,2,3</b>.</li> <li>For a single partition setup, leave this field blank.</li> </ul>                                                                                                                |
| Number of sessions during backup      | Specifies the number of sessions to use for the backup. You can back up database objects to the Avamar server or the Data Domain system in parallel by specifying 1 to 6 sessions. The use of multiple data streams for a backup can increase system performance when you back up a large database.                                                                                                                                                                     |
| Enable debugging messages             | Writes maximum information to log files. This option can create large log files.                                                                                                                                                                                                                                                                                                                                                                                        |

**Table 6** Backup plug-in options (continued)

| Option                                  | Description                                                                                                        |
|-----------------------------------------|--------------------------------------------------------------------------------------------------------------------|
| Store backup on Data Domain system      | Uses a Data Domain system that you select from the list to store the Avamar Plug-in for DB2 backup.                |
| Encryption method to Data Domain system | Specifies the encryption method for data transfer between the client and the Data Domain system during the backup. |

## Restore options

Restore plug-in options enable you to control restore functionality that is specific to the Avamar Plug-in for DB2. Restore options are set from the **Restore Command Line Options** dialog box.

The following table lists options for restore operations with the Avamar Plug-in for DB2.

**Table 7** Restore plug-in options

| Option                                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Encryption method from Data Domain system       | Specifies the encryption method for data transfer between the Data Domain system and the client during the restore.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| Recover                                         | Performs a db2 recover operation for the database.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Restore and roll forward database               | <p>For online backups that include archive logs, restores both the database and the archive logs, and then rolls the database forward. If you select the <b>Restore and roll forward database</b> option, you must also complete the following steps:</p> <ol style="list-style-type: none"> <li>1. Select an options from the <b>Type of Recovery</b> list other than the <b>End of backup</b> option. DB2 recover operations do not support the <b>End of backup</b> options.</li> <li>2. Specify a value in the <b>Directory Path to Restore Archive Logs</b> field.</li> </ol> <hr/> <p><b>Note</b></p> <p>The <b>Restore and roll forward database</b> option is not supported for database partition restore operations.</p> |
| Restore only                                    | Performs only a restore of the backups. Select this option to restore a backup without recovery, to restore offline backups, or to restore online backups that do not have archive logs.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
| Restore only archive logs from an online backup | Restores only the archive logs from the backup.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| Type of Recovery                                | <p>When you select the <b>Restore and roll forward database</b> option, select a recovery option from the list:</p> <ul style="list-style-type: none"> <li>• <b>End of logs</b>—Rolls the database forward until the end of the archive logs.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |

**Table 7** Restore plug-in options (continued)

| Option                                 | Description                                                                                                                                                                                                                                                                                                                                                                                             |
|----------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                        | <ul style="list-style-type: none"> <li>• <b>Point In Time</b>—Rolls the database forward until a certain point-in-time, which you specify in the <b>Date and Time</b> field.</li> <li>• <b>End of Backup</b>—Rolls the database forward until the end of the backup. This option is available only for DB2 version 9.5 and later. Do not specify this option with the <b>Recover</b> option.</li> </ul> |
| Date and Time                          | <p>When you select <b>Point In Time</b> from the <b>Type of Recovery</b> list, specify the recovery date and the time by using the following format:</p> <p><i>yyyy-mm-dd hh:mm:ss</i></p> <p>Specify the time that corresponds to the time zone of the client system.</p>                                                                                                                              |
| Number of sessions during restore      | Specifies the number of sessions to use for the restore. You can restore database objects in parallel by specifying one to ten sessions. The use of multiple data streams for a restore increases system performance when you back up a large amount of data. To obtain the best performance during a restore, use the same number of restore sessions that you used for the backup.                    |
| Instance Admin Username                | Specifies the instance owner or system admin username.                                                                                                                                                                                                                                                                                                                                                  |
| Instance Admin Password                | Specifies the instance owner's password.                                                                                                                                                                                                                                                                                                                                                                |
| Database Partition Numbers             | <p>Specifies a single-value database partition to use for the restore:</p> <ul style="list-style-type: none"> <li>• To specify a partition, type the database partition number.</li> <li>• To recover a single partition setup, leave this field blank.</li> </ul>                                                                                                                                      |
| Directory Path to Restore Archive Logs | Specifies the fully qualified pathname of an existing top-level directory. The restore operation creates a subdirectory below the directory pathname you specify and restores the archive logs to this subdirectory.                                                                                                                                                                                    |
| Database Name                          | Specifies the new name for the database when you perform a directed restore. DB2 supports database names that include up to eight characters.                                                                                                                                                                                                                                                           |
| Instance Name                          | Specifies the password for the username.                                                                                                                                                                                                                                                                                                                                                                |
| Enable debugging messages              | Writes maximum information to log files. This option can create large log files.                                                                                                                                                                                                                                                                                                                        |

## Table space restore option

You can restore a table space in offline mode. By default, a table space restore uses online mode. You can, however, restore a table space in offline mode by using the `tbs-offline-restore-mode` option. Set the `tbs-offline-restore-mode` option to `true` to perform a granular restore in offline mode.

## DB2 vendor parameters

You can use DB2 vendor parameters with `db2` commands by including them in a flag file. [Specifying DB2 vendor parameters on page 89](#) provides more information.

The following table lists parameters that you can specify in the flag file.

**Table 8** DB2 vendor parameters

| Parameter name                                | Description                                                                                                                                                                                                                                                                                                                                                   | Examples                                                                        |
|-----------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------|
| <code>--account</code>                        | Optional for all operations. Specifies the Avamar domain of the client. This domain is usually <code>/domain_name/client_hostname</code> .                                                                                                                                                                                                                    | <code>--account=/clients/user_pc</code>                                         |
| <code>--avtar-before-after-days-search</code> | Optional for restore operations. Specifies a search range (in number of days) for a backup image based on DB2 timestamp. The option is used to construct the time range in <code>avtar</code> history search for db2 backup image availability:<br><br>Begin on (timestamp - days)<br>end at (timestamp + days)                                               | <code>--avtar-before-after-days-search=3</code>                                 |
| <code>--catnode</code>                        | Mandatory for all operations in a DPF environment. Specifies the partition number of the catalog node.                                                                                                                                                                                                                                                        | <code>--catnode=0</code>                                                        |
| <code>--db2-source-instance</code>            | Mandatory for a redirected restore to a different instance. Specifies the name of the source instance.                                                                                                                                                                                                                                                        | <code>--db2-source-instance=db2inst1</code>                                     |
| <code>--dbpartitionnums</code>                | Mandatory for all operations in a DPF environment. Specifies the list of partitions for a single-system view. This parameter's setting must match the value of the <code>on dbpartitionnums list</code> option that you use with the <code>db2</code> command.                                                                                                | <code>--dbpartitionnums=0, 1, 2, 3</code><br><code>--dbpartitionnums=all</code> |
| <code>--ddr</code>                            | Optional. Specifies that an Avamar backup is to be saved to a Data Domain system.                                                                                                                                                                                                                                                                             | <code>--ddr=true</code>                                                         |
| <code>--ddr-index</code>                      | Mandatory when <code>--ddr</code> is set. Index number (1, 2, 3, or so forth) of the Data Domain system on which the backup is to be saved. An index number is assigned to the Data Domain system when it is added to the Avamar server configuration. Contact the Avamar administrator to determine the required index number. If you do not set this option | <code>--ddr-index=1</code>                                                      |



Table 8 DB2 vendor parameters (continued)

| Parameter name                  | Description                                                                                                                                                                                                                                                                                                                                                                                                                      | Examples                                                                                                                                                             |
|---------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                 | when the <code>--ddr</code> parameter is set, then the backup is not reported correctly.                                                                                                                                                                                                                                                                                                                                         |                                                                                                                                                                      |
| <code>--debug</code>            | Optional. Turns on debugging messages. Do not set this option for normal operations because this setting can create large log files.                                                                                                                                                                                                                                                                                             | <code>--debug=true</code>                                                                                                                                            |
| <code>--encrypt</code>          | Optional. Specifies the type of encryption to be used by <code>avtar</code> for a backup. The values supported for this parameter are <code>proprietary</code> , <code>ssl</code> , <code>sslverify</code> , <code>tcp</code> , <code>tls</code> , and <code>tls-sa</code> . The default value for all backups is <code>tls</code> .<br><br>The <i>EMC Avamar Product Security Guide</i> provides more details about encryption. | <code>--encrypt=ssl</code>                                                                                                                                           |
| <code>--encrypt-strength</code> | Optional. Specifies the level of encryption to be used by <code>avtar</code> for a backup. The values supported for this parameter are <code>high</code> , <code>medium</code> , and <code>cleartext</code> .<br><br>The default value for all backups is <code>high</code> .                                                                                                                                                    | <code>--encrypt-strength=high</code>                                                                                                                                 |
| <code>--expires</code>          | Optional. Specifies the backup expiration time in number of days. A backup with Avamar Administrator ignores this parameter if it is set in the flag file. The default value is defined by the End User On Demand Retention policy, which has a default value of 60 days.<br><br>The <i>EMC Avamar Administration Guide</i> provides more details about expiration.                                                              | <code>--expires=120</code>                                                                                                                                           |
| <code>--id</code>               | Mandatory for all operations. Specifies an Avamar server username that has Avamar Administrator privileges.                                                                                                                                                                                                                                                                                                                      | <code>--id=user-1@/clients/<br/>hostA.avamar.emc</code>                                                                                                              |
| <code>--labelnum</code>         | Mandatory for restore operations only, when you restore backups from Avamar releases before 7.0. Specifies backup label number.                                                                                                                                                                                                                                                                                                  | <code>--label=100</code>                                                                                                                                             |
| <code>--logdest-account</code>  | Optional parameter for rollforward operations following a redirected restore to a new host and for log backups on the new host. Specifies the account on the destination host that was used for a log backup.                                                                                                                                                                                                                    | <code>--logdest-account=/clients/<br/>hostA.avamar.emc.com</code>                                                                                                    |
| <code>--logdest-ap</code>       | Mandatory for rollforward operations following a redirected restore to a new host and for log backups on the new host. Specifies the password on the destination host for the user id that was used for a log backup. You can run the following <code>avtar</code> command on the command line to encode a password:                                                                                                             | <code>--logdest-ap=encoded_ password</code><br><br>The 80-character encoded value is the value returned by the <code>avtar --encodepassword=password</code> command. |

Table 8 DB2 vendor parameters (continued)

| Parameter name                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    | Examples                                                                                                                                                             |
|----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                  | <p><b>avtar --encodepassword=<i>password</i></b></p> <p>where <i>password</i> is the password that you type in clear text on the command line.</p> <p>The <b>avtar</b> command returns an encoded password that you can then use with the <b>--logdest-ap</b> parameter in the flag file.</p>                                                                                                                                                                                                                  |                                                                                                                                                                      |
| <b>--logdest-id</b>              | Mandatory for rollforward operations following a redirected restore to a new host and for log backups on the new host. Specifies the user id on the destination host that was used for a log backup.                                                                                                                                                                                                                                                                                                           | <b>--logdest-id=MCUser</b>                                                                                                                                           |
| <b>--logfile</b>                 | Optional parameter for all operations. Specifies the log file's location and prefix. If you do not specify the <b>--logfile</b> parameter, the log file's default location is <i>install_path</i> /var/clientlogs.                                                                                                                                                                                                                                                                                             | <b>--logfile=/usr/avamar/var/clientlogs/avdb2.log</b>                                                                                                                |
| <b>--password, pswd, or --ap</b> | <p>Mandatory for all operations. Specifies the password for the user name you specify with the <b>--id</b> parameter. You can run the following <b>avtar</b> command on the command line to encode a password:</p> <p><b>avtar --encodepassword=<i>password</i></b></p> <p>where <i>password</i> is the password that you type in clear text on the command line.</p> <p>The <b>avtar</b> command returns an encoded password that you can then use with the <b>--password</b> parameter in the flag file.</p> | <p><b>--password=encoded_ password</b></p> <p>The 80-character encoded value is the value returned by the <b>avtar --encodepassword=<i>password</i></b> command.</p> |
| <b>--retention-type</b>          | Optional. Specifies the backup retention type for a backup. This parameter defines the retention type only and does not override the expiration. A backup with Avamar Administrator ignores this parameter if it is set in the flag file. The default value is none. The <i>EMC Avamar Administration Guide</i> provides more information.                                                                                                                                                                     | <b>--retention-type=daily, weekly, monthly</b>                                                                                                                       |
| <b>--server or --hfsaddr</b>     | Optional for all operations. Specifies the DNS hostname or IP address of the Avamar server.                                                                                                                                                                                                                                                                                                                                                                                                                    | <b>--server=server_name.example.com</b>                                                                                                                              |
| <b>--sysdir</b>                  | Mandatory for all operations. Specifies the location of the Avamar <i>etc</i> directory.                                                                                                                                                                                                                                                                                                                                                                                                                       | <p>On AIX and Linux:<br/><b>--sysdir=/usr/local/avamar/etc</b></p> <p>On HP-UX and Solaris:<br/><b>--sysdir=/opt/AVMRCInt/etc</b></p>                                |

**Table 8** DB2 vendor parameters (continued)

| Parameter name | Description | Examples                                                             |
|----------------|-------------|----------------------------------------------------------------------|
|                |             | On Windows:<br><code>--sysdir="C:\Program Files\avs<br/>\etc"</code> |



# APPENDIX B

## Troubleshooting

This appendix includes the following topics:

- [Troubleshooting backup problems](#)..... 110
- [Troubleshooting installation and configuration problems](#)..... 110
- [Troubleshooting DB2 CLP backup and restore problems](#)..... 111
- [Troubleshooting restore problems](#)..... 114
- [Specifying backup and restore options as normal text](#)..... 116

## Troubleshooting backup problems

You can resolve some backup problems with the troubleshooting information in this appendix.

## Troubleshooting installation and configuration problems

You can resolve some installation and configuration problems with the troubleshooting information in this appendix.

### Installing the Avamar Plug-in for DB2 in the default directory fails

The Avamar Plug-in for DB2 must be installed in the same directory as the Avamar client software. Otherwise, the installation fails.

If you install the Avamar Plug-in for DB2 in the default directory on an AIX system, which has the Avamar client software installed in a nondefault directory, the installation fails with the following error:

```
The Avamar Client is located in '/usr/local/INSTALLPATH'.
Please re-run the DB2 plugin installer with the '-R /usr/local/
INSTALLPATH' flag
install: Failed while executing the AvamarDB2-aix6-ppc64.pre_i
script.
```

To resolve this problem, install the Avamar Plug-in for DB2 in the same directory as the Avamar Client for AIX:

```
installp -R install_path -d AvamarDB2-aix6-ppc64-version.bff all
```

where:

- *install\_path* is the directory for the installation files.
- *version* is the Avamar software version.

### Resolving a network hostname might result in a time-out error

You might receive a time-out error while the system tries to resolve the hostname of the client system that runs the DB2 server and Avamar Plug-in for DB2. The Avamar Plug-in for DB2 requires an unimpeded network connection to the Avamar server.

To establish a communication resource, typically requires hostname resolution either through DNS or by using the `/etc/hosts` file. A system's network configuration determines what method to use for hostname resolution. For example, a system might resolve a hostname by using the `/etc/hosts` file as the last method. In this case, the communication process might appear to be slow.

Ensure that the hostname resolution configuration is optimal on the host that runs the DB2 server and Avamar Plug-in for DB2. The documentation for the operation system provides more information about configuring hostname resolution.

## Troubleshooting DB2 CLP backup and restore problems

You can resolve some CLP backup and restore problems with the troubleshooting information in this appendix.

### Adjusting the time gap between DB2 CLP operations

You must set `--timeout-new-connection` option to allow enough time for CLP operations to complete.

After all data is successfully read, written, and processed for a CLP operation, the vendor call sequence completes. After the vendor call completes and the control of the CLP interface returns to the user, the `avdb2` process requires time to shut down and clean up resources before another CLP operation can begin. The time gap between CLP operations is approximately 1 to 2 minutes. This time gap can vary, but it must be large enough to include the time value specified by the `--timeout-new-connection` option.

### Backup does not complete in DPF configuration

In a DPF configuration, which uses a SLES system as the Avamar Plug-in for DB2 client system, insufficient RAM on the client system might prevent backups from completing.

A backup in a DPF configuration fails to complete on a SUSE Linux Enterprise Server 11 64-bit system.

To work around this issue, use the following command from the DB2 CLP:

```
db2 backup db dbname on all DBPARTITIONNUMS TO /path
```

If the backup command from the CLP does not complete, IBM recommends increasing RAM on the SLES system to 6 GB or more.

### Cleaning up processes and resources after a DB2 CLP operation

The 1 to 2 minute period in which the `avdb2` process has to terminate and clean up resources might not be enough time before a subsequent CLP operation begins.

The components that a DB2 CLP operation uses typically includes one `avdb2` process, allocated resources such as global named semaphores, and a semaphore-key port file for communication control management. Regardless of whether the CLP operation completes successfully or fails, the `avdb2` process must terminate and the operation must release allocated resources. Otherwise, the vendor plug-in communication and workflow are not synchronized for subsequent CLP operations.

After each CLP operation completes, there is a 1 to 2 minute period in which to terminate processes and clean up resources. In some instances, you might need to manually clean up the processes and allocated resources.

### DB2 CLP fails due to time-out in communication response

An operation from the DB2 CLP might fail if the communication response between the Avamar Plug-in for DB2 and the vendor times out. The connection and performance speed, or heavy task loads on the system might cause the time-out.

#### Adjusting the `avdb2-response-time-for-library` flag

The `--avdb2-response-time-for-library` flag, which is set to 200 by default, determines the amount of time the vendor library waits for a response from the Avamar

Plug-in for DB2. When the amount of time exceeds the time set by the `--avdb2-response-time-for-library` flag, a timeout occurs. The `--avdb2-response-time-for-library` flag also determines the amount of time the Avamar Plug-in for DB2 takes to start a DB2 CLP operation.

When the timeout setting is insufficient, vendor-plug-in communication errors might occur. The following error messages occur while waiting for the Avamar Plug-in for DB2 to start in response to a backup call:

```
2012-11-04 22:09:40 Error :File open failed
/usr/local/avamar/var/clientlogs/db2inst1-AVAMAR3-backup-sem
2012-11-04 22:09:40 Error :Could not get port number
```

Adjust the `--avdb2-response-time-for-library` flag, as necessary, to accommodate the performance and connection speed of the system and the task load on the system.

#### Adjusting the timeout-new-connection flag

The `--timeout-new-connection` flag is useful for DB2 CLP database-image and log restore operations. By default, the `--timeout-new-connection` flag is set to 5 seconds for database image operations and 60 seconds for log operations.

The Avamar Plug-in for DB2 terminates when it assumes there are no more requests or queries from the vendor library. For a DB2 backup or restore operation, there are multiple queries and requests from the vendor to the Avamar Plug-in for DB2 process. During a rollforward operation, for example, the DB2 software requires some time after it retrieves an archive log to apply the log. After the log is applied, the DB2 software can query for another log. The rollforward process, including the query and retrieval of logs, then continues.

The `--timeout-new-connection` flag controls the length of time the Avamar Plug-in for DB2 waits for new requests or queries from the vendor library until the operation is complete.

During an ongoing operation, when the time gap between the requests or queries exceeds the `--time-new-connection` value, the following error messages appear:

```
2013-02-21 10:23:01 Debug :AvLibCommThread::initComm()
2013-02-21 10:23:01 Error : Socket connection failed to host
[localhost] to port [53275] Error [239]
2013-02-21 10:23:01 Debug :initComm throws exception
2013-02-21 10:23:01 Debug :AvCommunicator failed with
[exception in AvLibCommThread::AvLibCommThread]
```

Adjust the `--timeout-new-connection` flag, as necessary, to allow the connection between the Avamar Plug-in for DB2 and vendor library enough time to complete the CLP operation.

## Recovery of a dropped database fails with error code 30

You cannot use the `recover db` command to recover a dropped database.

The following `recover db` command fails to recover a dropped database:

```
recover db avamar1 to end of logs using history file (/tmp/)
```

The recovery failure returns the following error message:

```
SQL2079N An error was reported by the shared library
"/opt/AVMRclnt/lib/libdb2_avamarloader.so". Return code: "30".
```



The Avamar Plug-in for DB2 does not support the `recover db` command for dropped databases.

To recover a dropped database, use the `restore` command, followed by the `rollforward` command:

1. Set the `VENDOROPT` parameter to the flag file:  

```
update db cfg for database_name using VENDOROPT @/pathname/avdb2.flg
```

where:

  - *database\_name* is the name of the database.
  - *pathname* is the directory that contains the Avamar Plug-in for DB2 flag file.
2. Restore the database by using the `restore` command.
3. Perform a rollforward operation.

## Using an invalid Avamar Plug-in for DB2 flag file returns an error

An invalid or missing Avamar Plug-in for DB2 flag file causes backup operations to fail.

A DB2 CLP operation fails with a SQL2062N error message when the Avamar Plug-in for DB2 flag file is invalid or missing. For example, the following backup operation fails:

```
db2 backup db cover01 load
/usr/local/avamar/lib/libdb2_avamarloader.so options
@/tmp/cli_test/wrong_file.cfg
```

This `db2 backup db` command returns the following error message:

```
SQL2062N An error occurred while accessing media
"/usr/local/avamar/lib/libdb2_avamarloader.so". Reason code:
"115".
```

You can obtain the description of the SQL message ID (SQL2062N) from the DB2 documentation or by using the following command:

```
db2 ? SQL2062N
```

## Use of signal handles does not cleanly stop DB2 CLP operations

The Avamar Plug-in for DB2 and vendor do not implement signal handlers. When a CLP operation receives an interrupt signal from a user or from a DB2 exception, the termination of the operation is not clean.

The `avdb2` process can stop responding and resources such as the global named semaphores and the semaphore-key port file might still be allocated to the CLP operation.

To resolve this issue, you must manually stop the `avdb2` process and clean up the allocated resources. You might also need to restart the database manager.

- The semaphore-key port file is located in the *Avamar\_install\_dir/var/clientlogs* directory.
- The semaphore-key-name file name is *instance\_name-DB\_name-operation-sem*, where operation is backup, restore, or log-restore.

On Linux, global named semaphores are created in a virtual file system and are normally mounted under `/dev/shm` with the name format: *sem.semaphore-key-name*.

## Troubleshooting restore problems

You can resolve some restore problems with the troubleshooting information in this appendix.

### Adjusting the base timeline for a log restore

During a rollforward operation, the Avamar Plug-in for DB2 uses the DB2 history backup time with a fallback of 10 minutes as the default base timeline when searching for the available logs. A 10-minute period might not allow enough search time for archived logs.

In the case of an online backup, the default fallback time includes the logs that were archived and saved before the database image was saved. The amount of fallback time that the search requires can vary depending on the size of the logs.

The `--fallback-mins-search` flag impacts the search time for a restore operation of archived logs. A database rollforward operation uses this flag when retrieving the archived logs to apply to the database after the restore and recovery of a database backup image completes.

Use the `--fallback-mins-search` flag to add more fallback time to the default fallback time of 10 minutes. You can specify a negative value to fall forward from the default base timeline.

### Recover fails if LOGARCHOPT1 is more than 30 characters

A database recovery operation records an entry for the archived log backup in the COMMENT field of db2 recovery history. This entry is the value of the LOGARCHOPT1 parameter.

The COMMENT field can contain 30 characters. If the value of the LOGARCHOPT1 parameter is greater than 30 characters, the rollforward operation might fail with an error similar to the following error:

```
SQL1268N Roll-forward recovery stopped due to error "SQL1042"
while retrieving log file "S0000001.LOG" for database "TEST" on
node "0"
```

To work around this issue, ensure that the LOGARCHOPT1 parameter does not exceed 30 characters:

1. Configure the LOGARCHOPT1 parameter by using the following command:

```
db2 update db cfg for database_name using logarchopt1 @pathname
```

where *database\_name* is the name of the database and *pathname* is the absolute pathname, which comprises no more than 30 characters.

This step reconfigures the LOGARCHOPT1 parameter.

2. Recover the database. For example:

```
db2 recover db database_name
```

3. Back up the database after the recover successfully completes. For example:

```
db2 backup db pathname load
/usr/local/avamar/lib/libdb2_avamarloader.so options @pathname
```

The step ensures that future recovery operations use the new setting for the LOGARCHOPT1 parameter.

## Restore fails with a “Failed to initiate the restore operation” error

The default setting of 30 seconds for the `--subprocesstimeoutsecs` option might not allow enough time for a restore to complete.

A restore operation fails and writes the following error to the log file:

```
Failed to initiate the restore operation
```

Complete the following steps to resolve this problem:

1. Set the `--subprocesstimeoutsecs` option and value for the restore operation. [Specifying backup and restore options as normal text on page 116](#) provides instructions.
2. Type `--[avdb2]subprocesstimeoutsecs` in the **Enter Attribute** field.
3. Type a value from 40 to 60 in the **Enter Attribute Value** field.  
The default value is 30 seconds.
4. Retry the restore operation.

## Restore fails while retrieving snapview and metadata

A restore operation from Avamar Administrator might fail when the Avamar Plug-in for DB2 retrieves snapview and metadata.

### Adjusting the snapupbrowsetimeoutsecs flag

During a restore operation from Avamar Administrator, the Avamar Plug-in for DB2 retrieves the snapview of the backup. Because the performance and connection speed of the client and the Avamar server vary from system to system, this retrieval process might require a shorter or longer time period to complete. For a busy system, the retrieval process might require up to 90 seconds. The `--snapupbrowsetimeoutsecs` flag, which is set to 30 seconds by default, determines the time-out value for the retrieval of the snapview. If the retrieval of the snapview does not have enough time to complete, the restore fails with the following error messages:

```
2013-01-30 19:28:43 avdb2 Info <6686>: Process 31757
(/usr/local/avamar/bin/avtar) for workorder
MOD-1359537051265#11#browse_avtar0 started
2013-01-30 19:28:52 avdb2 Info <10684>: Setting ctl message
version to 3 (from 1)
2013-01-30 19:28:52 avdb2 Info <16136>: Setting ctl max message
size to 268435456
2013-01-30 19:29:15 avdb2 Info <7932>: Processing db2inst1
/NODE0000/AVAMAR1
2013-01-30 19:29:21 avdb2 Error <9006>: DB2 returned database
alias parameter error -2040
2013-01-30 19:29:21 avdb2 Error <8965>: Restore of
db2inst1/NODE0000/AVAMAR1 aborted
...
2013-01-30 19:30:45 avdb2 Info <6688>: Process 31757
(/usr/local/avamar/bin/avtar) finished (code 158: cannot
establish connection with server (possible network or
DNS failure))
```

Adjust the `--snapupbrowsetimeoutsecs` flag, as necessary, to allow enough time for the retrieval of the snapview to complete.

### Adjusting the subprocesstimeoutsecs flag

During a restore operation from Avamar Administrator, the Avamar Plug-in for DB2 retrieves the metadata for the backup. For a busy system, this retrieval process might require up to 90 seconds. The `--subprocesstimeoutsecs` flag, which is set to 30 seconds by default, determines the time-out value for the retrieval of the metadata. If the retrieval of the metadata does not have enough time to complete, the restore fails with the following error messages:

```
2013-01-30 19:41:05 avdb2 Info <6686>: Process 31845
(/usr/local/avamar/bin/avtar) for workorder
MOD-1359537708751#meta_avtar1 started
2013-01-30 19:41:13 avdb2 Info <10684>: Setting ctl message
version to 3 (from 1)
2013-01-30 19:41:13 avdb2 Info <16136>: Setting ctl max message
size to 268435456
2013-01-30 19:41:35 avdb2 Error <12714>: Failed to initiate the
restore operation
```

## Restore fails when search for backup images takes too long

A restore operation from either Avamar Administrator or command line might fail if Avamar queries looking for backup images are taking too long because the search is based on the image name only. To optimize the search, you can specify the search time range.

Complete the following steps to resolve this problem:

1. Set the `--avtar-before-after-days-search` option and value (in days) for the restore operation.  
[Specifying backup and restore options as normal text on page 116](#) provides instructions.
2. Retry the restore operation.

## Specifying backup and restore options as normal text

To resolve certain backup or restore problems can require the use of special options that you must type in the **Enter Attribute** and **Enter Attribute Value** fields. These fields are available by clicking the **More** button in the **Backup Command Line Options** or the **Restore Command Line Options** dialog box.

You can specify options from either the **Backup Command Line Options** dialog box or the **Restore Command Line Options** dialog box. Precede an option name that you specify in the **Enter Attribute** field with the prefix, `[avdb2]`.

---

### Note

The Avamar software does not validate the text that you type in the **Enter Attribute** and **Enter Attribute Value** fields. Ensure that you type the options and values correctly.

---

### Procedure


1. From the **Backup Command Line Options** or the **Restore Command Line Options** dialog box, click the **More** button.  
 The dialog box expands to display the **Enter Attribute** and **Enter Attribute Value** fields.
2. Type the option name in the **Enter Attribute** field and the value for the option in the **Enter Attribute Value** field.

3. Click +.

The option and value appear in the area below the **Enter Attribute** and **Enter Attribute Value** fields.

4. To add more options for the backup or restore operation, repeat steps 2 and 3.

The following figure shows the dialog box after adding two options.



Additional information for on-demand backup and restore operations is available in [Chapter 3, Backup on page 37](#) and [Chapter 4, Restore and Recovery on page 49](#).



# GLOSSARY

## A

**activation** The process of passing the client ID (CID) back to the client, where it is stored in an encrypted file on the client file system.

**See also** client activation

**administrator** Person who normally installs, configures, and maintains software on network computers, and who adds users and defines user privileges.

**archive logs** Files that DB2 uses for rollforward recovery.

**Automatic storage management** A DB2 storage feature that enables storage management at the database level. The database manager is responsible for creating, extending, and adding containers as needed. The user specifies a group of storage devices for the database manager to control.

**avagent** The name of the *client agent* process.

**Avamar Administrator** A graphical management console software application that is used to remotely administer an Avamar system from a supported Windows or Linux client computer.

**Avamar client** A computer or workstation that runs Avamar software and accesses the Avamar server over a network connection. Avamar client software comprises a *client agent* and one or more *plug-ins*.

**Avamar server** The server component of the Avamar client/server system. Avamar server is a fault-tolerant, high-availability system that efficiently stores the backups from all protected clients. It also provides essential processes and services required for data restores, client access, and remote system administration. Avamar server runs as a distributed application across multiple networked storage nodes.

**avtar** The Avamar process that performs backups and restores.

## B

**backup** A point-in-time copy of client data that can be restored as individual files, selected data, or as an entire backup.

**browse** The process of viewing data that is available for backup on a client computer or restore from the Avamar server.

## C

**client activation** The process of passing the client ID (CID) back to the client, where it is stored in an encrypted file on the client file system.

**See also** activation

**client agent** A platform-specific software process that runs on the client and communicates with the Management Console Server (MCS) and with any plug-ins installed on that client.

**client registration** The process of establishing an identity with the Avamar server. When Avamar recognizes the client, it assigns a unique client ID (CID), which it passes back to the client during *client activation*.

**See also** registration

**cold backup** A backup performed while the database is offline.

## D

**database** A collection of data arranged for ease and speed of update, search, and retrieval by computer software.

**database partition** An independent part of a partitioned database with its own data, configuration files, indexes, and transaction logs.

**Data Domain system** Disk-based deduplication appliances and gateways that provide data protection and disaster recovery (DR) in the enterprise environment.

**Data Partition Feature (DPF)** A feature that enables the distribution of a DB2 UDB database across multiple servers in a cluster or on multiple nodes on massively parallel processors (MPP). You can distribute a DB2 database across several database partitions.

**dataset** A policy that defines a set of files, directories, and file systems for each supported platform that are included or excluded in backups across a group of clients. A dataset is a persistent and reusable Avamar policy that can be named and attached to multiple groups.

**DB2 instance** An independent environment where you create database objects and run applications run against the database objects.

**DD Boost** The API that Avamar clients use to access a Data Domain system. The Avamar client installation automatically installs the DD Boost API on the client computer. The Avamar server installation automatically installs the DD Boost API on the Avamar server.

**disaster recovery** Recovery from any disruptive situation, such as hardware failure or software corruption, in which ordinary data recovery procedures are not sufficient to restore a system and its data to normal day-to-day operations. A disaster recovery can be a *bare metal recovery*.

**DNS** Domain Name Server. A dynamic and distributed directory service for assigning domain names to specific IP addresses.

**domain** A feature in Avamar Administrator that is used to organize large numbers of clients into named areas of control and management.

## F

**file system** Software interface used to save, retrieve, and manage files on storage media by providing directory structures, data transfer methods, and file association.



## G

- granular recovery** An Avamar feature that enables you to restore a part of a backup rather than the entire backup. The Avamar Plug-in for DB2 enables you to restore table spaces from a backup.
- group** A level of organization in Avamar Administrator for one or more Avamar clients. All clients in an Avamar group use the same group policies, which include the *dataset*, *schedule*, and *retention policy*.
- group policy** The *dataset*, *schedule*, and *retention policy* for all clients in an Avamar group.

## H

- hot backup** A backup that you run while users are online and have access to the data that is being backed up.

## L

- LAN** Local Area Network.

## M

- MCS** Management console server. The server subsystem that provides centralized administration (scheduling, monitoring, and management) for the Avamar server. The MCS also runs the server-side processes used by *Avamar Administrator*.
- metadata** Data about the backup, including information about the original database files, the backup types, the date and time of the backup, and other information necessary for restore.

## P

- plug-in** Avamar client software that recognizes a particular kind of data resident on that client.
- plug-in options** Options that you specify during backup or restore to control backup or restore functionality.
- policy** A set of rules for client backups that can be named and applied to multiple groups. Groups have dataset, schedule, and retention policies.

## R

- recover** To restore data from a backup to a client disk and apply transaction logs to the data to make it consistent with a specific point-in-time.
- redirected restore** The process of restoring a backup to a different location than the original location where the backup occurred.

- registration** The process of establishing an identity with the Avamar server. When Avamar recognizes the client, it assigns a unique client ID (CID), which it passes back to the client during *client activation*.
- See also** client registration
- restore** An operation that retrieves one or more file systems, directories, files, or data objects from a backup and writes the data to a designated location.
- retention** The time setting to automatically delete backups on an Avamar server. Retention can be set to permanent for backups that should not be deleted from an Avamar server. Retention is a persistent and reusable Avamar policy that can be named and attached to multiple groups.
- rollforward** The process of updating a database or a table space by applying changes recorded in the database log files. You perform a rollforward operation after you restore a database backup.

## S

- schedule** The ability to control the frequency and the start and end time each day for backups of clients in a group. A schedule is a persistent and reusable Avamar policy that can be named and attached to multiple groups.
- snapview** A list of table spaces that are available for a granular restore. To view a snapview from Avamar Administrator, select the **Browse for Granular Restore** button.

## T

- table spaces** Containers within a database that store specific data. DB2 includes five table spaces, which DB2 names according to their usage: catalog, regular, large, system temporary, and user temporary. IBM DB2 documentation provides more information.
- transaction logs** Files that provide a history of updates that you make to a database. You use transaction logs to roll back a database to a previous state.

## U

- User Account Control (UAC)** A Windows feature available in Windows Server 2008 R2 and Windows Vista. UAC helps prevent unauthorized changes to the computer. When functions that could potentially affect a computer's operation are made, UAC prompts the user for permission or for an administrator's password before continuing with the task.